

---

# **GMT Software and Controls Data Product Files**

***Release 1.4-1***

**Chien Y. Peng**

**Sep 01, 2018**

# Contents

|          |   |           |
|----------|---|-----------|
| <b>1</b> | <b>Introduction</b>                                 | <b>1</b>  |
| <b>2</b> | <b>Acronyms</b>                                     | <b>2</b>  |
| <b>3</b> | <b>FITS-Standard Data Containers</b>                | <b>3</b>  |
| 3.1      | Primary HDU (PHDU)                                  | 3         |
| 3.2      | Extension HDU: Image                                | 4         |
| 3.3      | Extension HDU: ASCII Table                          | 5         |
| 3.4      | Extension HDU: Binary Table                         | 6         |
| <b>4</b> | <b>Common Data Product Patterns</b>                 | <b>7</b>  |
| 4.1      | Base Exposure Primary HDU (PHDU)                    | 7         |
| 4.2      | Base Exposure Extension HDU (EHDU)                  | 12        |
| 4.3      | Base Calibration Reference Table (CRT)              | 14        |
| <b>5</b> | <b>Calibration and Reference File Data Products</b> | <b>15</b> |
| 5.1      | Bias Frame (BIA)                                    | 15        |
| 5.2      | Dark Frame (DRK)                                    | 16        |
| 5.3      | Dome Flat Field (DFL)                               | 17        |
| 5.4      | Night Sky Flat Field (NFL)                          | 18        |
| 5.5      | Twilight Flat Field (TFL)                           | 19        |
| 5.6      | Background Illumination Pattern (ILM)               | 20        |
| 5.7      | Bad Pixel Mask (MSK)                                | 21        |
| 5.8      | Post Flash Image (FLS)                              | 22        |
| 5.9      | Analog to Digital Table (A2D)                       | 23        |
| 5.10     | Bad Pixel Table (BPX)                               | 24        |
| 5.11     | Detector Characteristics Table (DCT)                | 25        |
| 5.12     | Cosmic Ray Rejection Parameter (CRR)                | 27        |
| 5.13     | Image Distortion Coefficients (IDC)                 | 28        |
| 5.14     | Overscan Region (OSC)                               | 30        |
| 5.15     | Photometric Calibration (PHT)                       | 33        |
| 5.16     | Aperture Throughput Table (APT)                     | 35        |
| <b>6</b> | <b>Science and Operations Data Products</b>         | <b>37</b> |
| 6.1      | Raw Data (RAW)                                      | 37        |
| 6.2      | Wavelength Calibration Exposure (WAV)               | 38        |
| 6.3      | Template Calibration Lamp Spectra Table (LMP)       | 39        |
| 6.4      | Association Table (ASN)                             | 40        |
| 6.5      | Jitter File (JIF)                                   | 41        |
| 6.6      | Telescope Jitter File (JIT)                         | 42        |
| 6.7      | Aperture Description Table (APD)                    | 42        |
| 6.8      | 2D Spectrum Distortion Correction Table (SDC)       | 44        |
| 6.9      | Dispersion Coefficients Table (DSP)                 | 47        |
| 6.10     | 1D Spectrum Trace Table (1DT)                       | 49        |

|   |           |
|---|-----------|
| 6.11 1D Spectral Extraction Parameter Table (1DX) . . . . . | 51        |
| <b>7 References</b>   | <b>54</b> |

## INTRODUCTION

This report provides a list of the FITS data product files produced by the Data Processing Subsystem.

---

CHAPTER

TWO

---

ACRONYMS

## FITS-STANDARD DATA CONTAINERS

A minimum set of keywords are mandatory to define the FITS standard containers. The mandatory keywords shown below define empty storage containers. The mandatory keywords must appear in the numeric order shown below; no other keywords may intervene.

### 3.1 Primary HDU (PHDU)

**Description:** This is a basic model that defines the primary header data unit, or PRI, of a FITS container. This model creates an empty storage container.

**Format:** Position attribute ‘pos’ defines the order in the FITS header; 0 specifies no particular location. The last keyword in the header must be END.

**File:** <inst>\_PRI.fits

Table 3.1: Primary HDU: Basic FITS Primary Header Data Unit

| Keyword | Description   | Value/Table Format | Type    | HDU |
|---------|---|--------------------|---------|-----|
| SIMPLE  | Indicates whether the file conforms to the standard | T                  | boolean | PRI |
| BITPIX  | Bits per data value                                 | 8                  | integer | PRI |
| NAXIS   | Number of axes                                      | 2                  | integer | PRI |
| NAXIS1  | Size along the axis 1 dimension                     |                    | integer | PRI |
| NAXIS2  | Size along the axis 2 dimension                     |                    | integer | PRI |
| END     | Marks the end of the header keywords                |                    |         | PRI |

## 3.2 Extension HDU: Image

**Description:** This is a basic model that defines an empty FITS storage container for an image extension. This base ‘image’ defines an area of 1024 columns and 1024 rows.

**Format:** The header keywords must follow the order shown, i.e. the first keyword must be XTENSION = ‘IMAGE ‘, the second BITPIX = 16, and so on. The last keyword in the header must be END.

**File:** <inst>\_bing.fits

Table 3.2: Extension HDU: Basic FITS Image Extension

| Keyword  | Description  | Value/Table Format | Type    | HDU |
|----------|--|--------------------|---------|-----|
| EXTEND   | Indicates whether the FITS file contain extensions | T                  | boolean | PRI |
| XTENSION | Marks beginning of new HDU                         | IMAGE              | string  | EXT |
| BITPIX   | Bits per data value                                | 16                 | integer | EXT |
| NAXIS    | Number of axes                                     | 2                  | integer | EXT |
| NAXIS1   | Size along the axis 1 dimension                    |                    | integer | EXT |
| NAXIS2   | Size along the axis 2 dimension                    |                    | integer | EXT |
| PCOUNT   | Parameter Count                                    |                    | integer | EXT |
| GCOUNT   | Group count  | 1                  | integer | EXT |
| END      | Marks the end of the header keywords               |                    |         | EXT |

### 3.3 Extension HDU: ASCII Table

**Description:** This is a basic model that defines an empty FITS storage container for an ASCII table extension. An ASCII table can store catalogues and tables of data. Each row of the table has a fixed length of ASCII characters, divided into columns by TBCOLn. This base ‘table’ defines an area of ASCII text that has one column which is 80 characters wide and 100 rows deep.

**Format:** The header keywords must follow the order shown, i.e. the first keyword must be XTENSION = ‘TABLE ‘, the second BITPIX = 16, and so on. The last keyword in the header must be END.

**File:** <inst>\_atbl.fits

Table 3.3: Extension HDU: Base ASCII Table

| Keyword  | Description  | Value/Table Format | Type    | HDU |
|----------|--|--------------------|---------|-----|
| EXTEND   | Indicates whether the FITS file contain extensions | T                  | boolean | PRI |
| XTENSION | Marks beginning of new HDU                         | TABLE              | string  | EXT |
| BITPIX   | Bits per data value                                | 16                 | integer | EXT |
| NAXIS    | Number of axes                                     | 2                  | integer | EXT |
| NAXIS1   | Size along the axis 1 dimension                    |                    | integer | EXT |
| NAXIS2   | Size along the axis 2 dimension                    |                    | integer | EXT |
| PCOUNT   | Parameter Count                                    |                    | integer | EXT |
| GCOUNT   | Group count  | 1                  | integer | EXT |
| TFIELDS  | Number of columns in the table                     | 1                  | integer | EXT |
| TTYPE1   | Column name  |                    | string  | EXT |
| TBCOL1   | Beginning column number                            | 1                  | integer | EXT |
| TFORM1   | Column data format                                 |                    | string  | EXT |
| END      | Marks the end of the header keywords               |                    |         | EXT |



### 3.4 Extension HDU: Binary Table

**Description:** This is a basic model that defines an empty FITS storage container for an binary table extension. This base ‘table’ defines storage for 1 column and 100 rows of integers, where each row has 1024 bytes in width.

**Format:** The header keywords must follow the order shown, i.e. the first keyword must be XTENSION = ‘BINTABLE’, the second BITPIX = 16, and so on. The last keyword in the header must be END.

**File:** <inst>\_btbl.fits

Table 3.4: Extension HDU: Basic Binary Table Extension

| Keyword  | Description  | Value/Table Format | Type    | HDU |
|----------|--|--------------------|---------|-----|
| EXTEND   | Indicates whether the FITS file contain extensions | T                  | boolean | PRI |
| XTENSION | Marks beginning of new HDU                         | BINTABLE           | string  | EXT |
| BITPIX   | Bits per data value                                | 16                 | integer | EXT |
| NAXIS    | Number of axes                                     | 2                  | integer | EXT |
| NAXIS1   | Size along the axis 1 dimension                    |                    | integer | EXT |
| NAXIS2   | Size along the axis 2 dimension                    |                    | integer | EXT |
| PCOUNT   | Parameter Count                                    |                    | integer | EXT |
| GCOUNT   | Group count  | 1                  | integer | EXT |
| TFIELDS  | Number of columns in the table                     | 1                  | integer | EXT |
| TTYPE1   | Column name  | Col                | string  | EXT |
| TFORM1   | Column data format                                 | 1024I              | string  | EXT |
| TUNIT1   | Column units                                       | Counts             | string  | EXT |
| END      | Marks the end of the header keywords               |                    |         | EXT |

## COMMON DATA PRODUCT PATTERNS

This section contain keywords that are commonly found in uncalibrated and calibrated data products.

### 4.1 Base Exposure Primary HDU (PHDU)

**Description:** This is a basic model that specifies baseline headers that are found in an GMT exposure. This ought to be inherited by all imaging and spectroscopy exposures.

**Format:** Standard FITS Image

**File:** <inst>\_PRI.fits

Table 4.1: Primary HDU: Base Exposure

| Keyword       | Description   | Value/Table Format        | Type    | HDU |
|---------------|---|---------------------------|---------|-----|
| DATE          | Date of file creation                                   | YYYY-MM-DDTHH:MM:SS[.sss] | string  | PRI |
| IRAF-TLM      | (IRAF-TLM) Time of last modification [To be Deleted?]   |                           | string  | PRI |
| NEXTEND       | The number of standard extensions [To be Deleted?]      |                           | integer | PRI |
| ORIGIN        | Organization or person responsible for the data         |                           | string  | PRI |
| ROOTNAME      | Rootname of the observation set                         |                           | string  | PRI |
| FILENAME      | Name of the originating data file                       |                           | string  | PRI |
| FILETYPE      | Type of data found in data file (SCI, CALIB, RAW, etc.) |                           | string  | PRI |
| TELESCOP      | Name of telescope                                       | GMT                       | string  | PRI |
| INSTRUME      | Name of instrument                                      |                           | string  | PRI |
| EQUINOX       | Equinox of celestial coordinate system                  |                           | float   | PRI |
| PROPOSID      | Proposal ID   |                           | string  | PRI |
| pr_inv_l[TBD] | [TBD]   | [TBD]                     | [TBD]   | PRI |
| pr_inv_f[TBD] | [TBD]   | [TBD]                     | [TBD]   | PRI |
| pr_inv_m[TBD] | [TBD]   | [TBD]                     | [TBD]   | PRI |
| TARGNAME      | Target name   |                           | string  | PRI |
| OBJECT        | Name or type of observed object                         |                           | string  | PRI |
| RA_TARG       | Right ascension of the target in mean places of equinox |                           | float   | PRI |
| DEC_TARG      | Declination of the target in mean places of equinox     |                           | float   | PRI |

Continued on next page

Table 4.1 – continued from previous page

| Keyword   | Description  | Value/Table Format | Type    | HDU |
|-----------|--|--------------------|---------|-----|
| TEQUINOX  | Equinox of the target  |                    | float   | PRI |
| EXPNAME   | Exposure identifier  |                    | string  | PRI |
| DATE-OBS  | Date of the observation  | YYYY-MM-DD         | string  | PRI |
| TIME-OBS  | [Deprecated in favor of DATE-OBS]<br>UT time of start of observation<br>(hh:mm:ss)           | HH:MM:SS[.sss]     | string  | PRI |
| EXPSTART  | [Deprecated in favor of TSTART] Ex-<br>posure start time (Modified Julian<br>Date)           |                    | float   | PRI |
| EXPEND    | [Deprecated in favor of TSTOP] Expo-<br>sure end time (Modified Julian Date)                 |                    | float   | PRI |
| EXPTIME   | [Deprecated in favor of XPOSURE]<br>On-detector, open-shutter, integration<br>time (seconds) |                    | float   | PRI |
| NRPTEXP   | Number of repeat exposures in set: de-<br>fault 1  | 1                  | integer | PRI |
| CRSPLIT   | Number of cosmic ray split exposures   |                    | integer | PRI |
| QUALCOM1  | Data quality comment n   |                    | string  | PRI |
| QUALCOM2  | Data quality comment n   |                    | string  | PRI |
| QUALCOM3  | Data quality comment n   |                    | string  | PRI |
| QUALITY   | Data quality summary   |                    | string  | PRI |
| POSTARG1  | Telescope Offset in axis 1 direction<br>(usually x)  |                    | float   | PRI |
| POSTARG2  | Telescope Offset in axis 2 direction<br>(usually y)  |                    | float   | PRI |
| EQNX_OFF  | Equinox of the offset, in case different<br>from target equinox                              |                    | float   | PRI |
| OBSTYPE   | Observation type - imaging or spectro-<br>scopic   |                    | string  | PRI |
| OBSMODE   | GMT Observing mode   |                    | string  | PRI |
| PHOTMODE  | Observation configuration mode for<br>photometric calibration                                |                    | string  | PRI |
| SCLAMP    | Lamp status, NONE or name of lamp<br>which is on   |                    | string  | PRI |
| LAMP_ID   | Lamp ID  |                    | string  | PRI |
| LAMP_VOL  | Lamp voltage status  |                    | float   | PRI |
| SUBARRAY  | Data from a subarray (T) or full frame<br>(F)  | F                  | boolean | PRI |
| DETECTOR  | Detector name in use   |                    | string  | PRI |
| CMDGAIN   | Commanded A-to-D conversion gain of<br>detector  |                    | float   | PRI |
| OPT_ELEM  | Optical element in use   |                    | string  | PRI |
| PROPAPER  | Aperture specified in an observing pro-<br>posal   |                    | string  | PRI |
| APERTURE  | Aperture name  |                    | string  | PRI |
| APER_FOV  | Aperture field of view   |                    | string  | PRI |
| FILTER    | Filter name selected from filter wheel   |                    | string  | PRI |
| CENWAVE   | Proposed central wavelength of spec-<br>trum   |                    | integer | PRI |
| ATODGN\$1 | Measured gain for amplifier n  |                    | float   | PRI |

Continued on next page

Table 4.1 – continued from previous page

| Keyword    | Description   | Value/Table Format | Type    | HDU |
|------------|---|--------------------|---------|-----|
| RDNOISE\$1 | Measured readnoise for amplifier n                    |                    | float   | PRI |
| DETOFFSt   | Commanded detector bias offset                        |                    | string  | PRI |
| PLATESC    | Detector plate scale [arcsec]                         |                    |         | PRI |
| CENTERA1   | Subarray axis n center point in unbinned detector pix |                    | integer | PRI |
| SIZAXIS1   | Subarray axis n size in unbinned detector pixels      |                    | integer | PRI |
| SIZAXIS2   | Subarray axis n size in unbinned detector pixels      |                    | integer | PRI |
| BINAXIS1   | Axis n bin size in unbinned detector pixels           |                    | integer | PRI |
| BINAXIS2   | Axis n bin size in unbinned detector pixels           |                    | integer | PRI |
| BPIXTAB    | Bad pixel table                                       |                    | string  | PRI |
| DARKFILE   | Superdark image file name                             |                    | string  | PRI |
| PFLTFILE   | Pixel to pixel flatfield file name                    |                    | string  | PRI |
| DFLTFILE   | Delta flatfield file name                             |                    | string  | PRI |
| LFLTFILE   | Low order flat file                                   |                    | string  | PRI |
| FFLTFILE   | Fringe correction flat file                           |                    | string  | PRI |
| PHOTTAB    | Photometric throughput table                          |                    | string  | PRI |
| APERTAB    | Relative aperture throughput table                    |                    | string  | PRI |
| CCDTAB     | Detector calibration parameters                       |                    | string  | PRI |
| ATODTAB    | Analog to digital correction file                     |                    | string  | PRI |
| BIASFILE   | Superbias image file name                             |                    | string  | PRI |
| SHADFILE   | Shutter shading correction file                       |                    | string  | PRI |
| CRREJTAB   | Cosmic ray rejection parameter table                  |                    | string  | PRI |
| WAVECALF   | Wavelength image file name                            |                    | string  | PRI |
| SPTRCTAB   | Spectrum trace table                                  |                    | string  | PRI |
| DISPTAB    | Dispersion coefficient table                          |                    | string  | PRI |
| LAMPTAB    | Template calibration lamp spectra table               |                    | string  | PRI |
| SDCTAB     | 2-D spatial distortion correction table               |                    | string  | PRI |
| XTRACTAB   | Parameters for 1-D spectral extraction tab            |                    | string  | PRI |
| PCTAB      | Photometry correction table                           |                    | string  | PRI |
| WCPTAB     | Wavelength calibration parameter table                |                    | string  | PRI |
| ASN_ID     | Unique identifier assigned to association             |                    | string  | PRI |
| ASN_TAB    | Name of the association file                          |                    | string  | PRI |
| MEANEXP    | Reference exposure time for parameters                |                    | float   | PRI |
| SCALENSE   | Multiplicative scale factor applied to noise          |                    | float   | PRI |
| INITGUES   | Initial guess method (MIN or MED)                     |                    | string  | PRI |
| SKYSUB     | Sky value subtracted (MODE or NONE)                   |                    | string  | PRI |
| CRSIGMAS   | Statistical rejection criteria                        |                    | string  | PRI |
| CRRADIUS   | Rejection propagation radius (pixels)                 |                    | float   | PRI |
| CRTHRESH   | Rejection propagation threshold                       |                    | float   | PRI |
| BADINPDQ   | Data quality flag bits to reject                      |                    | integer | PRI |

Continued on next page

Table 4.1 – continued from previous page

| Keyword       | Description  | Value/Table Format | Type    | HDU |
|---------------|--|--------------------|---------|-----|
| REJ_RATE      | Rate at which pixels are affected by cosmic rays             |                    | float   | PRI |
| CRMASK        | Flag CR-rejected pixels in input files (T/F)                 |                    | boolean | PRI |
| PATTERN1      | Primary pattern type   |                    | string  | PRI |
| P1_SHAPE      | Primary pattern shape  |                    | string  | PRI |
| P1_PURPS      | Primary pattern purpose                                      |                    | string  | PRI |
| P1_NPTS       | Number of points in primary pattern                          |                    | integer | PRI |
| P1_PSPAC      | Point spacing for primary pattern (arc-sec)                  |                    | float   | PRI |
| P1_LSPAC      | Line spacing for primary pattern (arc-sec)                   |                    | float   | PRI |
| P1_ANGLE      | Angle between sides of parallelogram pattern (deg)           |                    | float   | PRI |
| P1_FRAME      | Coordinate frame of primary pattern                          | POS-TARG           | string  | PRI |
| P1_ORINT      | Orientation of pattern to coordinate frame (deg)             |                    | float   | PRI |
| P1_CENTR      | Center pattern relative to pointing (yes/no)                 | NO                 | string  | PRI |
| propttl1[TBD] | [TBD]  | [TBD]              | [TBD]   | PRI |
| OBSET_ID      | Observation set ID   |                    | string  | PRI |
| TARGDESC      | Target description   |                    | string  | PRI |
| PM_FLAG       | Does this target have proper motion?                         | F                  | boolean | PRI |
| PARALLAX      | Target parallax  |                    | float   | PRI |
| PM_RA         | Target proper motion in RA                                   |                    | float   | PRI |
| PM_DEC        | Target proper motion in DEC                                  |                    | float   | PRI |
| PM_EQNX       | Equinox of target proper motion                              |                    | string  | PRI |
| PA_V3         | Position angle of the V3 axis.                               |                    | float   | PRI |
| AIRMASS       | Airmass at the center of exposure                            |                    | float   | PRI |
| GS1_RA        | Right ascension of the guide stars in mean places of equinox |                    | float   | PRI |
| GS1_DEC       | Declination of the guide stars in mean places of equinox     |                    | float   | PRI |
| GS1_MAG       | Guide star magnitude   |                    | float   | PRI |
| GS1_FILT      | Passband of guide star magnitude                             |                    | string  | PRI |
| GS1_EQNX      | Equinox of the guidestars                                    |                    | float   | PRI |
| GS2_RA        | Right ascension of the guide stars in mean places of equinox |                    | float   | PRI |
| GS2_DEC       | Declination of the guide stars in mean places of equinox     |                    | float   | PRI |
| GS2_MAG       | Guide star magnitude   |                    | float   | PRI |
| GS2_FILT      | Passband of guide star magnitude                             |                    | string  | PRI |
| GS2_EQNX      | Equinox of the guidestars                                    |                    | float   | PRI |
| GS3_RA        | Right ascension of the guide stars in mean places of equinox |                    | float   | PRI |
| GS3_DEC       | Declination of the guide stars in mean places of equinox     |                    | float   | PRI |
| GS3_MAG       | Guide star magnitude   |                    | float   | PRI |
| GS3_FILT      | Passband of guide star magnitude                             |                    | string  | PRI |
| GS3_EQNX      | Equinox of the guidestars                                    |                    | float   | PRI |

Continued on next page

Table 4.1 – continued from previous page

| Keyword  | Description  | Value/Table Format | Type   | HDU |
|----------|--|--------------------|--------|-----|
| GS4_RA   | Right ascension of the guide stars in mean places of equinox |                    | float  | PRI |
| GS4_DEC  | Declination of the guide stars in mean places of equinox     |                    | float  | PRI |
| GS4_MAG  | Guide star magnitude   |                    | float  | PRI |
| GS4_FILT | Passband of guide star magnitude                             |                    | string | PRI |
| GS4_EQNX | Equinox of the guidestars                                    |                    | float  | PRI |
| PROCTIME | Pipeline processing time (MJD)                               |                    | float  | PRI |
| HISTORY  | Processing history of the data                               |                    | string | PRI |

## 4.2 Base Exposure Extension HDU (EHDU)

**Description:** This is a basic model that specifies baseline headers that are found in an GMT exposure. This ought to be inherited by all imaging and spectroscopy exposures.

**Format:** Standard FITS image extension

**File:** <inst>\_EXT.fits

Table 4.2: Extension HDU: Base Exposure

| Keyword   | Description  | Value/Table Format | Type    | HDU |
|-----------|--|--------------------|---------|-----|
| EXTNAME   | Name of the extension  |                    | string  | EXT |
| EXTVER    | Version of the extension   | 1                  | integer | EXT |
| IRAF-TLM  | (IRAF-TLM) Time of last modification<br>[To be Deleted?]             |                    | string  | EXT |
| INHERIT   | Indicates whether header of primary HDU is inherited into extensions |                    | boolean | EXT |
| EXPNAME   | Exposure identifier  |                    | string  | EXT |
| BUNIT     | Physical units of the array values                                   |                    | string  | EXT |
| ASN_MTYPE | Role of the member in the association                                |                    | string  | EXT |
| WCSAXES   | The number of axes in the WCS description                            |                    | integer | EXT |
| CRPIX1    | Coordinate system reference pixel                                    | 0.0                | float   | EXT |
| CRPIX2    | Coordinate system reference pixel                                    | 0.0                | float   | EXT |
| CRVAL1    | Coordinate system value at reference pixel                           | 0.0                | float   | EXT |
| CRVAL2    | Coordinate system value at reference pixel                           | 0.0                | float   | EXT |
| CTYPE1    | Name of the coordinate axis  |                    | string  | EXT |
| CTYPE2    | Name of the coordinate axis  |                    | string  | EXT |
| CD1_1     | Linear transformation matrix between axes i and j                    |                    | float   | EXT |
| CD1_2     | Linear transformation matrix between axes i and j                    |                    | float   | EXT |
| CD2_1     | Linear transformation matrix between axes i and j                    |                    | float   | EXT |
| CD2_2     | Linear transformation matrix between axes i and j                    |                    | float   | EXT |
| LTV1      | Offset in X to subsection start                                      |                    | float   | EXT |
| LTV2      | Offset in Y to subsection start                                      |                    | float   | EXT |
| LTM1_1    | Reciprocal of sampling rate in X                                     |                    | float   | EXT |
| LTM2_2    | Reciprocal of sampling rate in Y                                     |                    | float   | EXT |
| RA_APER   | Right ascension of aperture reference position                       |                    | float   | EXT |
| DEC_APER  | Declination of aperture reference position                           |                    | float   | EXT |
| PA_APER   | Position angle of reference aperture center (deg)                    |                    | float   | EXT |
| DISPAXIS  | Dispersion axis: 1= axis 1, 2 = axis 2, none                         |                    | string  | EXT |
| CUNIT1    | Units of CRVAL and CDELTA  |                    | string  | EXT |
| CUNIT2    | Units of CRVAL and CDELTA  |                    | string  | EXT |

Continued on next page

Table 4.2 – continued from previous page

| Keyword  | Description  | Value/Table Format | Type    | HDU |
|----------|--|--------------------|---------|-----|
| ORIENTAT | Position angle of image Y-axis (degrees East of North)                                 |                    | float   | EXT |
| SUNANGLE | Angle between sun and z-axis   |                    | float   | EXT |
| MOONANGL | Angle between moon and z-axis  |                    | float   | EXT |
| SUN_ALT  | Altitude of the sun  |                    | float   | EXT |
| REFFRAME | Guide star catalog version   |                    | string  | EXT |
| DATE-OBS | Date of the observation  | YYYY-MM-DD         | string  | EXT |
| TIME-OBS | [Deprecated in favor of DATE-OBS] UT time of start of observation (hh:mm:ss)           | HH:MM:SS[.sss]     | string  | EXT |
| EXPSTART | [Deprecated in favor of TSTART] Exposure start time (Modified Julian Date)             |                    | float   | EXT |
| EXPEND   | [Deprecated in favor of TSTOP] Exposure end time (Modified Julian Date)                |                    | float   | EXT |
| EXPTIME  | [Deprecated in favor of XPOSURE] On-detector, open-shutter, integration time (seconds) |                    | float   | EXT |
| EXPFLAG  | Exposure interrupt indicator   |                    | string  | EXT |
| RV_HELIO | Target heliocentric radial velocity  |                    | float   | EXT |
| PATTSTEP | Position number of this point in the pattern   |                    | integer | EXT |
| NCOMBINE | Number of image sets combined, such as during CR rejection, or for any other purpose   |                    | integer | EXT |
| NGOODPIX | Number of good pixels  |                    | integer | EXT |
| SDQFLAGS | Serious data quality flags   |                    | integer | EXT |
| GOODMIN  | Minimum value of good pixels   |                    | float   | EXT |
| GOODMAX  | Maximum value of good pixels   |                    | float   | EXT |
| SNRMIN   | Minimum signal-to-noise of good pixels   |                    | float   | EXT |
| SNRMAX   | Maximum signal-to-noise of good pixels   |                    | float   | EXT |
| SNRMEAN  | Mean value of signal-to-noise of good pixels   |                    | float   | EXT |
| SOFTERRS | Number of soft error pixels (DQF1)   |                    | integer | EXT |
| MEANDARK | Average dark level subtracted  |                    | float   | EXT |
| MEANBLEV | Average bias level subtracted  |                    | float   | EXT |
| SPORDER  | Spectral order   |                    | integer | EXT |



### 4.3 Base Calibration Reference Table (CRT)

**Description:** This is a basic model that specifies baseline headers for GMT calibration reference tables.

**Format:** Standard FITS binary table

**File:** <inst>\_crt.fits

Table 4.3: Extension HDU: Base Calibration Reference Table

| Keyword      | Description  | Value/Table Format        | Type    | HDU |
|--------------|--|---------------------------|---------|-----|
| EXTEND       | Indicates whether the FITS file contain extensions                   | T                         | boolean | PRI |
| TELESCOP     | Name of telescope  | GMT                       | string  | PRI |
| INSTRUME     | Name of instrument   |                           | string  | PRI |
| DATE         | Date of file creation  | YYYY-MM-DDTHH:MM:SS[.sss] | string  | PRI |
| FILETYPE     | Type of data found in data file (SCI, CALIB, RAW, etc.)              | BASE CALIB TA-<br>BLE     | string  | PRI |
| USE_DATE     | Use this file for obs taken on or after this date                    | YYYY-MM-DD                | string  | PRI |
| descrip[TBD] | [TBD]  | [TBD]                     | [TBD]   | PRI |
| APERTURE     | Aperture name  |                           | string  | PRI |
| CENWAVE      | Proposed central wavelength of spectrum                              |                           | integer | PRI |
| XTENSION     | Marks beginning of new HDU   | BINTABLE                  | string  | EXT |
| BITPIX       | Bits per data value  | 16                        | integer | EXT |
| PCOUNT       | Parameter Count  | 0                         | integer | EXT |
| GCOUNT       | Group count  | 1                         | integer | EXT |
| TFIELDS      | Number of columns in the table                                       |                           | integer | EXT |
| EXTNAME      | Name of the extension  | CRT                       | string  | EXT |
| EXTVER       | Version of the extension   | 1                         | integer | EXT |
| INHERIT      | Indicates whether header of primary HDU is inherited into extensions | T                         | boolean | EXT |
| END          | Marks the end of the header keywords                                 |                           |         | EXT |

## CALIBRATION AND REFERENCE FILE DATA PRODUCTS

This Section summarizes a list of baseline calibration reference images and tables produced by the data processing system (DPS). GMT calibration reference data products (images and tables) are those used by the DPS to pipeline-process or calibrate science and telescope operations data. The keywords below supplement the mandatory FITS standard keywords and the Common Data Product patterns, thus are not repeated here.

### 5.1 Bias Frame (BIA)

**Description:** This is an image of the electronic zeropoint-level of an instrument, obtained with all light sources turned off, the detector shutter closed, and zero-second (or shortest possible) integration time. Usually, multiple (>10) bias images are taken at the beginning and/or end of the night and combined into one image. The file for the combined bias frame has the ‘bia’ suffix; pre-combined bias frames have a ‘raw’ suffix. The combined bias image is removed from the science images, usually as the first step in the data reduction.

**Format:** For both a single and multi-chip detector, the combined bias image is stored as an multi-extension file, with each set corresponding to each detector chip. If it is possible to change the binning mode of a detector, the binning factors are given by BINAXIS1 and BINAXIS2 header parameters. The bias image [SCI] and the error array [ERR] have raw detector data units (DN), such that  $GAIN * DN = \text{electrons}$ .

**File:** <inst>\_bia.fits

Table 5.1: Data Product HDU: Bias Frame

| Keyword  | Description   | Value/Table Format | Type   | HDU |
|----------|---|--------------------|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | BIAS               | string | PRI |
| EXTNAME  | Name of the extension                                   | BIA                | string | PRI |
| OBSTYPE  | Observation type - imaging or spectroscopic             | IMAGING            | string | PRI |
| FILTER   | Filter name selected from filter wheel                  | CLEAR              | string | PRI |
| BUNIT    | Physical units of the array values                      | DN                 | string | PRI |

## 5.2 Dark Frame (DRK)

**Description:** This image records the dark-current signal of an instrument, obtained with ambient light turned off, the detector shutter closed. Typically, multiple dark exposures are taken at the beginning and/or end of the night, using different integration time settings. After subtracting out the bias, the individual dark images are combined into one and normalized to 1 second. The file for the combined dark frame has the “drk” suffix; pre-combined dark frames have a “raw” suffix. When applying dark correction to a science image, the combined dark image is scaled to the exposure time of the science image and removed, usually either as the second (after bias subtraction) or third (after overscan correction, if relevant) step in the data reduction.

**Format:** A combined dark image is stored as an MEF of the type shown in Figure 5-1 for an optical/UV detector, and Figure 5 2 for a NIR detector. When it is possible to change the binning mode of a detector, the binning factors are given by BINAXIS1 and BINAXIS2 header parameters. The dark image [SCI] and the error array [ERR] have raw detector data units per second (DN/sec), such that  $GAIN * DN = \text{electrons/sec}$ , for both UVIS and IR images. The header keyword EXPTIME = 1 is set to indicate the normalization.

Two flags in the [DQ] extension that potentially are present are 16 (hot pixels) and 128 (bad reference pixels, for IR detectors). Other, more permanent flags, e.g. dead and unstable pixels, should be stored in the bad pixel table (suffix “BPX”) file. IR detectors – For IR detectors, the SAMP and the TIME image extensions (see Figure 5 2) are used to calculate the total exposure times (TIME \* SAMP) at each pixel. The SAMP extension gives the total number of retained input samples after image combination, and is an image. The TIME extension gives the total open shutter exposure time at that readout sequence and is a single value for all pixels, thus the exposure time is stored as a PIXVALUE keyword value and not as EXPTIME (==1.0).

NUMEXPOS is intended for NIR MEF, where the keyword in the PRI contains the number of sets.

PIXVALUE is used for the TIME extension, for image exposure time.

SAMP\_SEQ, for NIR data, name the sampling sequence for a MULTIACCUM readout.

**File:** <inst>\_drk.fits

Table 5.2: Data Product HDU: Dark Frame

| Keyword       | Description  | Value/Table Format | Type   | HDU |
|---------------|--|--------------------|--------|-----|
| FILETYPE      | Type of data found in data file (SCI, CALIB, RAW, etc.)                                | DARK               | string | PRI |
| EXTNAME       | Name of the extension  | DRK                | string | PRI |
| OBSTYPE       | Observation type - imaging or spectroscopic  | IMAGING            | string | PRI |
| FILTER        | Filter name selected from filter wheel   | CLEAR              | string | PRI |
| numexpos[TBD] | [TBD]  | [TBD]              | [TBD]  | PRI |
| BUNIT         | Physical units of the array values   | DN/s               | string | PRI |
| PIXVALUE      | Value of all the pixels in a uniform image   |                    | float  | EXT |
| EXPTIME       | [Deprecated in favor of XPOSURE] On-detector, open-shutter, integration time (seconds) | 1                  | float  | EXT |
| SAMP_SEQ      | MULTIACCUM exposure time sequence name   |                    | string | EXT |

## 5.3 Dome Flat Field (DFL)

**Description:** The dome-flat is an image that records the pixel-to-pixel response of a detector, using a bright artificial light source in the dome to provide the illumination. Dome flats contain wavelength-dependent information about the uniformity of the detector response. After bias and dark subtraction, the combined dome flat is divided from the science images for calibration.

**Format:** A combined dome image is stored as an MEF of the type shown in Figure 5-1 for all optical/UV and NIR detectors, with only a single set of extension HDUs. The suffix “DFL” is used only for combined flat; individual raw flatfield images have the “RAW” suffix.

The median of the pixel value distribution is normalized to 1.

**File:** <inst>\_dfl.fits

Table 5.3: Data Product HDU: Dome Flat Field Frame

| Keyword  | Description   | Value/Table Format | Type   | HDU |
|----------|---|--------------------|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | DOMESTAT           | string | PRI |
| EXTNAME  | Name of the extension                                   | DFL                | string | PRI |
| OBSTYPE  | Observation type - imaging or spectroscopic             | IMAGING            | string | PRI |
| FILTER   | Filter name selected from filter wheel                  | CLEAR              | string | PRI |
| BUNIT    | Physical units of the array values                      | DN                 | string | PRI |
| LAMP_ID  | Lamp ID   |                    | string | PRI |
| LAMP_VOL | Lamp voltage status                                     |                    | float  | PRI |

## 5.4 Night Sky Flat Field (NFL)

**Description:** A night-sky flatfield is an image that records the pixel-to-pixel response of a detector using sky observations. Night-sky flatfields contain wavelength-dependent information about the uniformity of the detector response. They are similar to twilight-sky flats (or “twiflats,” suffix TFL, Appendix B.01f), except they are taken in the middle of the night rather than near sunrise or sunset for twiflats. The images used to combine night-sky flats may sometimes be intended for other purposes, such as science images themselves. Often, night-sky flats are observed immediately surrounding the intended science images. Night-sky and twi-flats may be derived using different data processing procedures. After bias and dark subtraction, the combined flat is divided from the science images for calibration.

**Format:** A combined night-sky flatfield image is stored as an MEF of the type shown in Figure 5-1 for all optical/UV and NIR detectors, with only a single set of extension HDUs. The suffix “NFL” is used only for combined flat; individual raw flatfield images have the “RAW” suffix.

Median of the pixel value distribution is normalized to 1.

**File:** <inst>\_nfl.fits

Table 5.4: Data Product HDU: Night-Sky Flat Field Frame

| Keyword  | Description   | Value/Table Format | Type   | HDU |
|----------|---|--------------------|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | NIGHT SKY FLAT     | string | PRI |
| EXTNAME  | Name of the extension                                   | NFL                | string | PRI |
| OBSTYPE  | Observation type - imaging or spectroscopic             | IMAGING            | string | PRI |
| FILTER   | Filter name selected from filter wheel                  | CLEAR              | string | PRI |
| BUNIT    | Physical units of the array values                      | DN                 | string | PRI |

## 5.5 Twilight Flat Field (TFL)

**Description:** A twilight sky-flat (or ‘twiflats’) is an image that records the pixel-to-pixel response of a detector using sky observations. Twiflats contain wavelength-dependent information about the uniformity of the detector response, and by definition are taken close to sunset or sunrise. The distinction between night-sky flatfield, dome flats, and twiflats should be made clear, as different data processing procedures are sometimes involved. After bias and dark subtraction, the combined flat is divided into the science images for calibration.

**Format:** A combined twiflat image is stored as a multi-extension file for all optical/UV and NIR detectors, with only a single set of extension HDUs. The suffix ‘TFL’ is used only for combined flat; individual raw flatfield images have the ‘RAW’ suffix.

**File:** <inst>\_tfl.fits

Table 5.5: Data Product HDU: Twilight Flat Field Frame

| Keyword  | Description   | Value/Table Format   | Type   | HDU |
|----------|---|----------------------|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | TWILIGHT SKY<br>FLAT | string | PRI |
| EXTNAME  | Name of the extension                                   | TFL                  | string | PRI |
| OBSTYPE  | Observation type - imaging or spectroscopic             | IMAGING              | string | PRI |
| FILTER   | Filter name selected from filter wheel                  | CLEAR                | string | PRI |
| BUNIT    | Physical units of the array values                      | DN                   | string | PRI |

## 5.6 Background Illumination Pattern (ILM)

**Description:** This is an image of spatially variable background illumination pattern. Correcting for the background pattern involves dividing the illumination image from data. When the signal is low, the background illumination pattern file is sometimes constructed using multiple (potentially science) images with object rejection, or by smoothing the background illumination pattern image. Details of image combination and smoothing are stored under the header keyword HISTORY, or potentially in a data processing trailer file.

**Format:** A background illumination file is stored as an MEF of the type shown in Figure 5 1 for all optical/UV and NIR detectors. The suffix “ILM” is used only for combined illumination file; individual raw flatfield images have the “RAW” suffix.

**File:** <inst>\_ilm.fits

Table 5.6: Data Product HDU: Background Illumination Pattern Frame

| Keyword  | Description   | Value/Table Format      | Type   | HDU |
|----------|---|-------------------------|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | ILLUMINATION<br>PATTERN | string | PRI |
| EXTNAME  | Name of the extension                                   | ILM                     | string | PRI |
| OBSTYPE  | Observation type - imaging or spectroscopic             | IMAGING                 | string | PRI |
| FILTER   | Filter name selected from filter wheel                  | CLEAR                   | string | PRI |
| BUNIT    | Physical units of the array values                      | DN                      | string | PRI |

## 5.7 Bad Pixel Mask (MSK)

**Description:** This is an image of all known, long-term, bad pixels for a detector. It is an image counterpart the “Bad Pixel Table (BPX)” discussed in Appendix B.02b. Transient hot pixels or cosmic rays detected during data reduction are stored in the data quality extension (DQ) of an MEF, or in the dark current reference file (file suffix “DRK”), depending on the purpose. The pixel values correspond to the data quality file as shown in Table 5-2.

**Format:** The coordinate origin of the bad pixel image is at the lower left corner after trimming the overscan region. The types of bad pixels recorded and their code values are:

4 – dead pixels

8 – deviant zeroth read (NIR) or bad pixel in bias (UVIS)

32 – unstable (NIR)

512 – bad in flatfield

These values are reflected in the data quality extensions during data processing.

**File:** <inst>\_msk.fits

Table 5.7: Data Product HDU: Bad Pixel Mask Frame

| Keyword  | Description   | Value/Table Format       | Type   | HDU |
|----------|---|--------------------------|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | STATIC BAD<br>PIXEL MASK | string | PRI |
| EXTNAME  | Name of the extension                                   | MSK                      | string | PRI |
| OBSTYPE  | Observation type - imaging or spectroscopic             | IMAGING                  | string | PRI |
| FILTER   | Filter name selected from filter wheel                  | CLEAR                    | string | PRI |
| BUNIT    | Physical units of the array values                      |                          | string | PRI |



## 5.8 Post Flash Image (FLS)

**Description:** A post-flash image corrects for the signal added to CCD exposures after a post-flash procedure. Correcting for post-flash signal involves: scaling the reference image in exposure time and gain to the science image, followed by image subtraction.

**Format:** A post-flash reference is an MEF of the same FITS data structure, image dimension and binning factor, as the science image. Like the raw science image, it consists of both the physical and virtual overscan regions.

**File:** <inst>\_fls.fits

Table 5.8: Data Product HDU: Post Flash Image

| Keyword     | Description   | Value/Table Format | Type   | HDU |
|-------------|---|--------------------|--------|-----|
| FILETYPE    | Type of data found in data file (SCI, CALIB, RAW, etc.) | POST FLASH         | string | PRI |
| EXTNAME     | Name of the extension                                   | FLS                | string | PRI |
| OBSTYPE     | Observation type - imaging or spectroscopic             | IMAGING            | string | PRI |
| FILTER      | Filter name selected from filter wheel                  | CLEAR              | string | PRI |
| BUNIT       | Physical units of the array values                      | DN                 | string | PRI |
| detamp[TBD] | [TBD]   | [TBD]              | [TBD]  | PRI |

## 5.9 Analog to Digital Table (A2D)

**Description:** This table provides a more detailed account of the A-to-D gain of a detector, i.e. number of actual counts (electrons) for each detected count (ADU) in an image, than provided in the image header keyword GAIN. This table is useful when the actual, measured, gain of a detector drifts with respect to an independent variable (REF\_NAME), such as the exposure time, despite the nominal GAIN setting. The values of the independent variable are stored in the REF\_VALUE array while the corresponding actual gain values are in ATOD.

Format:

**File:** <inst>\_a2d.fits

Table 5.9: Data Product HDU: Analog-to-Digital Table

| Keyword  | Description   | Value/Table Format | Type   | HDU |
|----------|---|--------------------|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | ANALOG TO DIGITAL  | string | PRI |
| EXTNAME  | Name of the extension                                   | A2D                | string | EXT |
| XTENSION | Marks beginning of new HDU                              | BINTABLE           | string | EXT |
| TTYPE1   | Column name   | DETAMP             | string | EXT |
| TFORM1   | Column data format                                      | A4                 | string | EXT |
| TDISP1   | Display format  | A4                 | string | EXT |
| TTYPE2   | Column name   | CMDGAIN            | string | EXT |
| TFORM2   | Column data format                                      | I2                 | string | EXT |
| TDISP2   | Display format  | I2.1               | string | EXT |
| TUNIT2   | Column units  | Integer            | string | EXT |
| TTYPE3   | Column name   | DETCIP             | string | EXT |
| TFORM3   | Column data format                                      | I1                 | string | EXT |
| TDISP3   | Display format  | I1.1               | string | EXT |
| TTYPE4   | Column name   | NELEM              | string | EXT |
| TFORM4   | Column data format                                      | I2                 | string | EXT |
| TDISP4   | Display format  | I2.1               | string | EXT |
| TTYPE5   | Column name   | REF_NAME           | string | EXT |
| TFORM5   | Column data format                                      | A12                | string | EXT |
| TDISP5   | Display format  | A12                | string | EXT |
| TTYPE6   | Column name   | REF_VALUE          | string | EXT |
| TFORM6   | Column data format                                      | I2                 | string | EXT |
| TDISP6   | Display format  | I2.1               | string | EXT |
| TTYPE7   | Column name   | ATODGAIN           | string | EXT |
| TFORM7   | Column data format                                      | F5.2               | string | EXT |
| TDISP7   | Display format  | F5.2               | string | EXT |
| TTYPE8   | Column name   | DATESTAMP          | string | EXT |
| TFORM8   | Column data format                                      | A10                | string | EXT |
| TDISP8   | Display format  | A10                | string | EXT |
| TTYPE9   | Column name   | TIMESTAMP          | string | EXT |
| TFORM9   | Column data format                                      | A12                | string | EXT |
| TDISP9   | Display format  | A12                | string | EXT |
| TTYPE10  | Column name   | DESCRIP            | string | EXT |
| TFORM10  | Column data format                                      | A67                | string | EXT |
| TDISP10  | Display format  | A67                | string | EXT |

## 5.10 Bad Pixel Table (BPX)

**Description:** A bad pixel table contains a list on all known, long-term, bad pixels for a detector. This is the table counterpart of the “Static Bad Pixel Image (MSK)” discussed in Appendix B.01i. Transient hot pixels or cosmic rays detected during data reduction are stored in the data quality extension (DQ) of an MEF, or in the dark current reference file (file suffix “DRK”), depending on the purpose.

Format:

**File:** <inst>\_bpx.fits

Table 5.10: Data Product HDU: Bad Pixel Table

| Keyword  | Description   | Value/Table Format | Type   | HDU |
|----------|---|--------------------|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | BAD PIXEL          | string | PRI |
| EXTNAME  | Name of the extension                                   | BPX                | string | EXT |
| XTENSION | Marks beginning of new HDU                              | BINTABLE           | string | EXT |
| TTYPE1   | Column name   | DETAMP             | string | EXT |
| TFORM1   | Column data format                                      | A4                 | string | EXT |
| TDISP1   | Display format  | A4                 | string | EXT |
| TTYPE2   | Column name   | XPOS               | string | EXT |
| TFORM2   | Column data format                                      | I5                 | string | EXT |
| TDISP2   | Display format  | I5.1               | string | EXT |
| TTYPE3   | Column name   | YPOS               | string | EXT |
| TFORM3   | Column data format                                      | I5                 | string | EXT |
| TDISP3   | Display format  | I5.1               | string | EXT |
| TTYPE4   | Column name   | VALUE              | string | EXT |
| TFORM4   | Column data format                                      | I4                 | string | EXT |
| TDISP4   | Display format  | I4.1               | string | EXT |
| TTYPE5   | Column name   | DESCRIP            | string | EXT |
| TFORM5   | Column data format                                      | A67                | string | EXT |
| TDISP5   | Display format  | A67                | string | EXT |

## 5.11 Detector Characteristics Table (DCT)

**Description:** A detector can have several readout modes, distinguished by readout speed, gain, bias level, binning factor settings, which an observer may manually set to optimize observations. Each readout mode is associated with a set of calibrated values in gain, bias level, readnoise, saturation level, etc.. For example, faster readout speeds usually result in higher readnoise. This master table stores information that maps a selected readout mode setting with measured performance parameters.

**Format:** In the FITS table, each row corresponds to a readout configuration. Each row is uniquely specified by the following parameters: the readout amplifiers configuration (AMPCONFIG), the detector chip (DETCCHIP), speed of the readout (RDSPEED), commanded gain (CMDGAIN), commanded bias (CMDBIAS), and chip binning factors (BINAXIS1, BINAXIS2), as well as the date and time stamps (DATESTAMP, TIMESTAMP). The actual measured parameters for the readout modes are the bias levels (BIASA through BIASD), gain (ATODGNA through ATODGND), and readnoise (RDNOISEA through RDNOISED).

The table below show an example where a detector chip is read out by 4 amplifiers (A-D), each amplifier reading out one quadrant. The AMPX and AMPY keywords indicate the dividing rows and columns of the quadrants. For example, For a 4096x4096 pixels in area, AMPX=2049 and AMPY=2049 indicate that the first quadrant runs from rows and columns 1-2048, while the fourth quadrant runs from 2049-4096 rows and columns.

**File:** <inst>\_dct.fits

Table 5.11: Data Product HDU: Detector Characteristics Table

| Keyword  | Description   | Value/Table Format            | Type   | HDU |
|----------|---|-------------------------------|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | DETECTOR CHAR-<br>ACTERISTICS | string | PRI |
| EXTNAME  | Name of the extension                                   | DCT                           | string | PRI |
| TTYPE1   | Column name   | DETAMP                        | string | EXT |
| TFORM1   | Column data format                                      | A4                            | string | EXT |
| TDISP1   | Display format  | A4                            | string | EXT |
| TTYPE2   | Column name   | DETCCHIP                      | string | EXT |
| TFORM2   | Column data format                                      | I1                            | string | EXT |
| TDISP2   | Display format  | I1.1                          | string | EXT |
| TTYPE3   | Column name   | RDSPEED                       | string | EXT |
| TFORM3   | Column data format                                      | A4                            | string | EXT |
| TDISP3   | Display format  | A4                            | string | EXT |
| TTYPE4   | Column name   | CMDGAIN                       | string | EXT |
| TFORM4   | Column data format                                      | I2                            | string | EXT |
| TDISP4   | Display format  | I2.1                          | string | EXT |
| TTYPE5   | Column name   | CMDBIASA                      | string | EXT |
| TFORM5   | Column data format                                      | F5                            | string | EXT |
| TDISP5   | Display format  | F5.2                          | string | EXT |
| TTYPE6   | Column name   | CMDBIASB                      | string | EXT |
| TFORM6   | Column data format                                      | F5                            | string | EXT |
| TDISP6   | Display format  | F5.2                          | string | EXT |
| TTYPE7   | Column name   | CMDBIASC                      | string | EXT |
| TFORM7   | Column data format                                      | F5                            | string | EXT |
| TDISP7   | Display format  | F5.2                          | string | EXT |
| TTYPE8   | Column name   | CMDBIASD                      | string | EXT |
| TFORM8   | Column data format                                      | F5                            | string | EXT |
| TDISP8   | Display format  | F5.2                          | string | EXT |
| TTYPE9   | Column name   | BINAXIS1                      | string | EXT |

Continued on next page

Table 5.11 – continued from previous page

| Keyword | Description        | Value/Table Format | Type   | HDU |
|---------|--------------------|--------------------|--------|-----|
| TFORM9  | Column data format | I2                 | string | EXT |
| TDISP9  | Display format     | I2.1               | string | EXT |
| TTYPE10 | Column name        | BINAXIS2           | string | EXT |
| TFORM10 | Column data format | I2                 | string | EXT |
| TDISP10 | Display format     | I2.1               | string | EXT |
| TTYPE11 | Column name        | BIASA              | string | EXT |
| TFORM11 | Column data format | F5                 | string | EXT |
| TDISP11 | Display format     | F5.2               | string | EXT |
| TTYPE12 | Column name        | BIASB              | string | EXT |
| TFORM12 | Column data format | F5                 | string | EXT |
| TDISP12 | Display format     | F5.2               | string | EXT |
| TTYPE13 | Column name        | BIASC              | string | EXT |
| TFORM13 | Column data format | F5                 | string | EXT |
| TDISP13 | Display format     | F5.2               | string | EXT |
| TTYPE14 | Column name        | BIASD              | string | EXT |
| TFORM14 | Column data format | F5                 | string | EXT |
| TDISP14 | Display format     | F5.2               | string | EXT |
| TTYPE15 | Column name        | ATODGNA            | string | EXT |
| TFORM15 | Column data format | F5                 | string | EXT |
| TDISP15 | Display format     | F5.2               | string | EXT |
| TTYPE16 | Column name        | ATODGNB            | string | EXT |
| TFORM16 | Column data format | F5                 | string | EXT |
| TDISP16 | Display format     | F5.2               | string | EXT |
| TTYPE17 | Column name        | ATODGNC            | string | EXT |
| TFORM17 | Column data format | F5                 | string | EXT |
| TDISP17 | Display format     | F5.2               | string | EXT |
| TTYPE18 | Column name        | ATODGND            | string | EXT |
| TFORM18 | Column data format | F5                 | string | EXT |
| TDISP18 | Display format     | F5.2               | string | EXT |
| TTYPE19 | Column name        | RDNOISEA           | string | EXT |
| TFORM19 | Column data format | F5                 | string | EXT |
| TDISP19 | Display format     | F5.2               | string | EXT |
| TTYPE20 | Column name        | RDNOISEB           | string | EXT |
| TFORM20 | Column data format | F5                 | string | EXT |
| TDISP20 | Display format     | F5.2               | string | EXT |
| TTYPE21 | Column name        | RDNOISEC           | string | EXT |
| TFORM21 | Column data format | F5                 | string | EXT |
| TDISP21 | Display format     | F5.2               | string | EXT |
| TTYPE22 | Column name        | RDNOISED           | string | EXT |
| TFORM22 | Column data format | F5                 | string | EXT |
| TDISP22 | Display format     | F5.2               | string | EXT |
| TTYPE23 | Column name        | AMPA               | string | EXT |
| TFORM23 | Column data format | I6                 | string | EXT |
| TDISP23 | Display format     | I6.1               | string | EXT |
| TTYPE24 | Column name        | AMPB               | string | EXT |
| TFORM24 | Column data format | I6                 | string | EXT |
| TDISP24 | Display format     | I6.1               | string | EXT |

## 5.12 Cosmic Ray Rejection Parameter (CRR)

**Description:** This table contains the parameters used to identify pixels affected by cosmic-rays (CR) when observed data images are split into multiple sub-exposures for the purpose. The affected pixels are marked for rejection in the data quality (DQ) extension of individual frames. The identification process begins by median-combining or minimum thresholding a list of CR-split images (FILTScheme) to estimate the background sky level (SKY-SUB) and noise (SCALENSE) values. Those pixels above a certain threshold value given by CRTHRESH and CRSIGMAS are identified as being cosmic-ray hit. If CRMASK is set to 'Y', then the CR-hit pixels take on values given by BADINDPDQ in the DQ extension of the affected image. If CRRADIUS is specified, then neighboring pixels are also identified as being affected.

Format:

**File:** <inst>\_crr.fits

Table 5.12: Data Product HDU: Cosmic Ray Rejection Parameters

| Keyword  | Description   | Value/Table Format   | Type   | HDU |
|----------|---|----------------------|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | COSMIC RAY REJECTION | string | PRI |
| EXTNAME  | Name of the extension                                   | CRR                  | string | PRI |
| XTENSION | Marks beginning of new HDU                              | BINABLE              | string | EXT |
| TTYPE1   | Column name   | DETCIP               | string | EXT |
| TFORM1   | Column data format                                      | I1                   | string | EXT |
| TDISP1   | Display format  | I1.1                 | string | EXT |
| TTYPE2   | Column name   | CRSPLIT              | string | EXT |
| TFORM2   | Column data format                                      | I2                   | string | EXT |
| TDISP2   | Display format  | I2.1                 | string | EXT |
| TTYPE3   | Column name   | MEANEXP              | string | EXT |
| TFORM3   | Column data format                                      | I2                   | string | EXT |
| TDISP3   | Display format  | I2.1                 | string | EXT |

## 5.13 Image Distortion Coefficients (IDC)

**Description:** This reference table contains information on geometric distortion models for generic imaging detectors. More specifically, the table contains coefficients and values for a polynomial that maps the coordinates from a raw image (distorted) to an undistorted space and vice versa.

**Format:** The format for the image distortion coefficient table is shown in Table B-22. The header keyword NORDER indicates the order of the polynomial and the number of coefficients used in the transformation.

**File:** <inst>\_idc.fits

Table 5.13: Data Product HDU: Image Distortion Coefficients

| Keyword     | Description   | Value/Table Format            | Type   | HDU |
|-------------|---|-------------------------------|--------|-----|
| FILETYPE    | Type of data found in data file (SCI, CALIB, RAW, etc.) | DISTORTION CO-EFFICIENTS      | string | PRI |
| EXTNAME     | Name of the extension                                   | IDC                           | string | PRI |
| XTENSION    | Marks beginning of new HDU                              | BINABLE                       | string | EXT |
| norder[TBD] | [TBD]   | [TBD]                         | [TBD]  | EXT |
| parity[TBD] | [TBD]   | [TBD]                         | [TBD]  | EXT |
| TTYPE1      | Column name   | DECHIP                        | string | EXT |
| TFORM1      | Column data format                                      | I1                            | string | EXT |
| TDISP1      | Display format  | I1.1                          | string | EXT |
| TTYPE2      | Column name   | DIRECTION                     | string | EXT |
| TFORM2      | Column data format                                      | I2                            | string | EXT |
| TDISP2      | Display format  | I2.1                          | string | EXT |
| TTYPE3      | Column name   | FILTER                        | string | EXT |
| TFORM3      | Column data format                                      | A10                           | string | EXT |
| TDISP3      | Display format  | A10                           | string | EXT |
| TTYPE4      | Column name   | XSIZE                         | string | EXT |
| TFORM4      | Column data format                                      | I5                            | string | EXT |
| TDISP4      | Display format  | I5.1                          | string | EXT |
| TUNIT4      | Column units  | pixel                         | string | EXT |
| TDESC4      | Column description                                      | Raw image size in X-direction | string | EXT |
| TTYPE5      | Column name   | YSIZE                         | string | EXT |
| TFORM5      | Column data format                                      | I5                            | string | EXT |
| TDISP5      | Display format  | I5.1                          | string | EXT |
| TUNIT5      | Column units  | pixel                         | string | EXT |
| TDESC5      | Column description                                      | Raw image size in Y-direction | string | EXT |
| TTYPE6      | Column name   | XREF                          | string | EXT |
| TFORM6      | Column data format                                      | F10                           | string | EXT |
| TDISP6      | Display format  | F10.6                         | string | EXT |
| TUNIT6      | Column units  | pixel                         | string | EXT |
| TDESC6      | Column description                                      | X position of reference point | string | EXT |
| TTYPE7      | Column name   | YREF                          | string | EXT |
| TFORM7      | Column data format                                      | F10                           | string | EXT |
| TDISP7      | Display format  | F10.6                         | string | EXT |
| TUNIT7      | Column units  | pixel                         | string | EXT |
| TDESC7      | Column description                                      | Y position of reference point | string | EXT |

Continued on next page

Table 5.13 – continued from previous page

| Keyword | Description        | Value/Table Format                             | Type   | HDU |
|---------|--------------------|--|--------|-----|
| TTYPE8  | Column name        | THETA  | string | EXT |
| TFORM8  | Column data format | F10  | string | EXT |
| TDISP8  | Display format     | F10.6  | string | EXT |
| TUNIT8  | Column units       | arcsec   | string | EXT |
| TDESC8  | Column description | Scale of square corrected pixel                | string | EXT |
| TTYPE9  | Column name        | V2REF  | string | EXT |
| TFORM9  | Column data format | F10  | string | EXT |
| TDISP9  | Display format     | F10.6  | string | EXT |
| TUNIT9  | Column units       | arcsec   | string | EXT |
| TDESC9  | Column description | V2 position of reference point [Axis name TBC] | string | EXT |
| TTYPE10 | Column name        | V3REF  | string | EXT |
| TFORM10 | Column data format | F10  | string | EXT |
| TDISP10 | Display format     | F10.6  | string | EXT |
| TUNIT10 | Column units       | arcsec   | string | EXT |
| TDESC10 | Column description | V3 position of reference point [Axis name TBC] | string | EXT |
| TTYPE11 | Column name        | CX10   | string | EXT |
| TFORM11 | Column data format | F10.6  | string | EXT |
| TDISP11 | Display format     | F10.6  | string | EXT |
| TDESC11 | Column description | Distortion coefficients for X position         | string | EXT |
| TTYPE12 | Column name        | CX11   | string | EXT |
| TFORM12 | Column data format | F10.6  | string | EXT |
| TDISP12 | Display format     | F10.6  | string | EXT |
| TDESC12 | Column description | Distortion coefficients for X position         | string | EXT |
| TTYPE13 | Column name        | CY10   | string | EXT |
| TFORM13 | Column data format | F10.6  | string | EXT |
| TDISP13 | Display format     | F10.6  | string | EXT |
| TDESC13 | Column description | Distortion coefficients for Y position         | string | EXT |
| TTYPE14 | Column name        | CY11   | string | EXT |
| TFORM14 | Column data format | F10.6  | string | EXT |
| TDISP14 | Display format     | F10.6  | string | EXT |
| TDESC14 | Column description | Distortion coefficients for Y position         | string | EXT |



## 5.14 Overscan Region (OSC)

**Description:** The overscan region table defines: the physical and virtual overscan locations on a detector, the locations of the bias sections, and the regions to trim during data processing. Each row in the table corresponds to a readout configuration, which is uniquely identified by the following table columns: DETAMP, DETCHIP, BINX, BINY, and NX, NY (see Table B 24).

The table columns TRIMXn and TRIMYn give the number of columns/rows to trim off at the beginning/end of each image columns/rows during data processing. As such they completely specify the physical overscan region for each chip. The region of the image that remains after trimming off TRIMXn and TRIMYn from NX and NY is the full aperture on a detector for science imaging.

The columns BIASSECTA1 and BIASSECTA2 give the beginning and ending columns to use for computing the bias level in the leading overscan region. Likewise, the BIASSECTB1 and BIASSECTB2 columns are used for the trailing overscan region. Finally, the virtual overscan window starts at pixel (VX1, VY1) and extends to (VX2, VY2).

All coordinates and column numbers refer to those in the untrimmed, raw, image.

NOTE: This would most likely have to be revisited for each detector, but this is the general idea. . . .

Format:

**File:** <inst>\_osc.fits

Table 5.14: Data Product HDU: Overscan Region

| Keyword  | Description   | Value/Table Format  | Type   | HDU |
|----------|---|---|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | OVERSCAN  | string | PRI |
| EXTNAME  | Name of the extension                                   | OSC   | string | PRI |
| XTENSION | Marks beginning of new HDU                              | BINABLE   | string | EXT |
| TTYPE1   | Column name   | DETAMP  | string | EXT |
| TFORM1   | Column data format                                      | A4  | string | EXT |
| TDISP1   | Display format  | A4  | string | EXT |
| TTYPE2   | Column name   | DETCIP  | string | EXT |
| TFORM2   | Column data format                                      | I1  | string | EXT |
| TDISP2   | Display format  | I1.1  | string | EXT |
| TTYPE3   | Column name   | BINX  | string | EXT |
| TFORM3   | Column data format                                      | I2  | string | EXT |
| TDISP3   | Display format  | I2.1  | string | EXT |
| TDESC3   | Column description                                      | Commanded bin size for axis 1   | string | EXT |
| TTYPE4   | Column name   | BINY  | string | EXT |
| TFORM4   | Column data format                                      | I2  | string | EXT |
| TDISP4   | Display format  | I2.1  | string | EXT |
| TDESC4   | Column description                                      | Commanded bin size for axis 2   | string | EXT |
| TTYPE5   | Column name   | TRIMX   | string | EXT |
| TFORM5   | Column data format                                      | I2  | string | EXT |
| TDISP5   | Display format  | I2.1  | string | EXT |
| TDESC5   | Column description                                      | Number of overscan columns to trim off beginning and end of each line | string | EXT |

Continued on next page

Table 5.14 – continued from previous page

| Keyword | Description        | Value/Table Format  | Type   | HDU |
|---------|--------------------|---|--------|-----|
| TTYPE6  | Column name        | TRIMY   | string | EXT |
| TFORM6  | Column data format | I2  | string | EXT |
| TDISP6  | Display format     | I2.1  | string | EXT |
| TDESC6  | Column description | Number of overscan rows to trim off beginning and end of each line                    | string | EXT |
| TTYPE7  | Column name        | BIASSECTA1  | string | EXT |
| TFORM7  | Column data format | I5  | string | EXT |
| TDISP7  | Display format     | I5.1  | string | EXT |
| TDESC7  | Column description | Beginning column in the leading section for estimating the bias level in the overscan | string | EXT |
| TTYPE8  | Column name        | BIASSECTA2  | string | EXT |
| TFORM8  | Column data format | I5  | string | EXT |
| TDISP8  | Display format     | I5.1  | string | EXT |
| TDESC8  | Column description | Ending column in the leading section for estimating the bias level in the overscan    | string | EXT |
| TTYPE9  | Column name        | BIASSECTB1  | string | EXT |
| TFORM9  | Column data format | I5  | string | EXT |
| TDISP9  | Display format     | I5.1  | string | EXT |
| TDESC9  | Column description | Beginning row in the leading section for estimating the bias level in the overscan    | string | EXT |
| TTYPE10 | Column name        | BIASSECTB2  | string | EXT |
| TFORM10 | Column data format | I5  | string | EXT |
| TDISP10 | Display format     | I5.1  | string | EXT |
| TDESC10 | Column description | Ending row in the leading section for estimating the bias level in the overscan       | string | EXT |
| TTYPE11 | Column name        | VX1   | string | EXT |
| TFORM11 | Column data format | I5  | string | EXT |
| TDISP11 | Display format     | I5.1  | string | EXT |
| TDESC11 | Column description | X coordinate of the origin of the virtual overscan region                             | string | EXT |
| TTYPE12 | Column name        | VX2   | string | EXT |
| TFORM12 | Column data format | I5  | string | EXT |
| TDISP12 | Display format     | I5.1  | string | EXT |
| TDESC12 | Column description | Y coordinate of the origin of the virtual overscan region                             | string | EXT |
| TTYPE13 | Column name        | VY1   | string | EXT |
| TFORM13 | Column data format | I5  | string | EXT |

Continued on next page

Table 5.14 – continued from previous page

| Keyword | Description        | Value/Table Format  | Type   | HDU |
|---------|--------------------|---|--------|-----|
| TDISP13 | Display format     | I5.1  | string | EXT |
| TDESC13 | Column description | X coordinate of the top corner of the virtual overscan region | string | EXT |
| TTYPE14 | Column name        | VY2   | string | EXT |
| TFORM14 | Column data format | I5  | string | EXT |
| TDISP14 | Display format     | I5.1  | string | EXT |
| TDESC14 | Column description | Y coordinate of the top corner of the virtual overscan region | string | EXT |
| TTYPE15 | Column name        | DATESTAMP   | string | EXT |
| TFORM15 | Column data format | A10   | string | EXT |
| TDISP15 | Display format     | A10   | string | EXT |
| TDESC15 | Column description | Date stamp  | string | EXT |
| TTYPE16 | Column name        | TIMESTAMP   | string | EXT |
| TFORM16 | Column data format | A12   | string | EXT |
| TDISP16 | Display format     | A12   | string | EXT |
| TDESC16 | Column description | Time stamp  | string | EXT |

## 5.15 Photometric Calibration (PHT)

**Description:** This reference file contains photometry keywords and calibrated values: PHOTMODE, PHOTFLAM, PHOTFNU, PHOTZPT, PHOTPLAM, PHOTBW for an instrument camera and filter combination used in an observation. If the science image has units in [DN sec<sup>-1</sup>], multiplying the pixel value by PHOFLAM or PHOTFNU yields absolute source fluxes in [ergs sec<sup>-1</sup> cm<sup>-2</sup> Ang<sup>-1</sup>] or [Jy], respectively.

**Format:** The photometry parameters file consists the columns shown in Table B-26. The PHOTMODE string is a comma-separated string of: instrument name, camera name/number, and filter or grating name. The HISTORY keyword in the HDU header or a trailer file contains detailed information on the calibration files used to derive the photometric parameters.

**File:** <inst>\_pht.fits

Table 5.15: Data Product HDU: Photometric Calibration

| Keyword  | Description   | Value/Table Format           | Type   | HDU |
|----------|---|------------------------------|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | PHOTOMETRIC CALIBRATION      | string | PRI |
| EXTNAME  | Name of the extension                                   | PHT                          | string | EXT |
| XTENSION | Marks beginning of new HDU                              | BINABLE                      | string | EXT |
| TTYPE1   | Column name   | PHOTMODE                     | string | EXT |
| TFORM1   | Column data format                                      | A19                          | string | EXT |
| TDISP1   | Display format  | A19                          | string | EXT |
| TDESC1   | Column description                                      | Instrument observing mode    | string | EXT |
| TTYPE2   | Column name   | PHOTFLAM                     | string | EXT |
| TFORM2   | Column data format                                      | E10                          | string | EXT |
| TDISP2   | Display format  | E10.5                        | string | EXT |
| TUNIT2   | Column units  | ergs/cm <sup>2</sup> /Ang/DN | string | EXT |
| TDESC2   | Column description                                      | Inverse sensitivity          | string | EXT |
| TTYPE3   | Column name   | PHOTFNU                      | string | EXT |
| TFORM3   | Column data format                                      | E10                          | string | EXT |
| TDISP3   | Display format  | E10.5                        | string | EXT |
| TUNIT3   | Column units  | Jy sec DN <sup>-1</sup>      | string | EXT |
| TDESC3   | Column description                                      | Inverse sensitivity          | string | EXT |
| TTYPE4   | Column name   | PHOTPLAM                     | string | EXT |
| TFORM4   | Column data format                                      | E10                          | string | EXT |
| TDISP4   | Display format  | E10.5                        | string | EXT |
| TUNIT4   | Column units  | Angstrom                     | string | EXT |
| TDESC4   | Column description                                      | Inverse sensitivity          | string | EXT |
| TTYPE5   | Column name   | PHOTBW                       | string | EXT |
| TFORM5   | Column data format                                      | E10                          | string | EXT |
| TDISP5   | Display format  | E10.5                        | string | EXT |
| TUNIT5   | Column units  | Angstrom                     | string | EXT |
| TDESC5   | Column description                                      | Bandwidth                    | string | EXT |
| TTYPE6   | Column name   | PHOTZPT                      | string | EXT |
| TFORM6   | Column data format                                      | E10                          | string | EXT |
| TDISP6   | Display format  | E10.5                        | string | EXT |
| TUNIT6   | Column units  | mag                          | string | EXT |
| TDESC6   | Column description                                      | Photometric zero-point       | string | EXT |
| TTYPE7   | Column name   | DATESTAMP                    | string | EXT |

Continued on next page

Table 5.15 – continued from previous page

| Keyword | Description        | Value/Table Format | Type   | HDU |
|---------|--------------------|--------------------|--------|-----|
| TFORM7  | Column data format | A10                | string | EXT |
| TDISP7  | Display format     | A10                | string | EXT |
| TDESC7  | Column description | Date stamp         | string | EXT |
| TTYPER8 | Column name        | TIMESTAMP          | string | EXT |
| TFORM8  | Column data format | A12                | string | EXT |
| TDISP8  | Display format     | A12                | string | EXT |
| TDESC8  | Column description | Time stamp         | string | EXT |

## 5.16 Aperture Throughput Table (APT)

**Description:** This is a table containing the wavelength-dependent transmission of each aperture with respect to a nominated reference aperture.

**Format:** The columns consist of: Aperture ID, number of elements in the throughput array, wavelength array, array of system throughput at corresponding wavelength, pedigree (datestamp) of reference data, and description. The suffix 'APT' is used to denote the file type.

**File:** <inst>\_apt.fits

Table 5.16: Data Product HDU: Aperture Throughput Table

| Keyword  | Description   | Value/Table Format                         | Type   | HDU |
|----------|---|--|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | APERTURE<br>THROUGHPUT<br>TABLE            | string | PRI |
| OBSTYPE  | Observation type - imaging or spectroscopic             | SPECTROSCOPIC                              | string | PRI |
| XTENSION | Marks beginning of new HDU                              | BINABLE                                    | string | EXT |
| EXTNAME  | Name of the extension                                   | APT  | string | EXT |
| TTYPE1   | Column name   | APERTURE                                   | string | EXT |
| TFORM1   | Column data format                                      | A19  | string | EXT |
| TDISP1   | Display format  | A19  | string | EXT |
| TDESC1   | Column description                                      | Aperture name                              | string | EXT |
| TTYPE2   | Column name   | NELEM                                      | string | EXT |
| TFORM2   | Column data format                                      | I6   | string | EXT |
| TDISP2   | Display format  | I6.1                                       | string | EXT |
| TUNIT2   | Column units  |  | string | EXT |
| TDESC2   | Column description                                      | Number of data points in throughput array  | string | EXT |
| TTYPE3   | Column name   | WAVELENGTH                                 | string | EXT |
| TFORM3   | Column data format                                      | E12  | string | EXT |
| TDISP3   | Display format  | E12.7                                      | string | EXT |
| TUNIT3   | Column units  | Angstrom                                   | string | EXT |
| TDESC3   | Column description                                      | Reference wave-length array                | string | EXT |
| TTYPE4   | Column name   | THROUGHPUT                                 | string | EXT |
| TFORM4   | Column data format                                      | F6   | string | EXT |
| TDISP4   | Display format  | F6.4                                       | string | EXT |
| TUNIT4   | Column units  | percent                                    | string | EXT |
| TDESC4   | Column description                                      | Total system throughput at each wavelength | string | EXT |
| TTYPE5   | Column name   | DATESTAMP                                  | string | EXT |
| TFORM5   | Column data format                                      | A67  | string | EXT |
| TDISP5   | Display format  | A67  | string | EXT |
| TUNIT5   | Column units  | date                                       | string | EXT |
| TDESC5   | Column description                                      | Date stamp                                 | string | EXT |
| TTYPE6   | Column name   | DESCRIP                                    | string | EXT |
| TFORM6   | Column data format                                      | A67  | string | EXT |
| TDISP6   | Display format  | A67  | string | EXT |

Continued on next page

Table 5.16 – continued from previous page

| Keyword | Description        | Value/Table Format            | Type   | HDU |
|---------|--------------------|-------------------------------|--------|-----|
| TDESC6  | Column description | Description of reference data | string | EXT |

## SCIENCE AND OPERATIONS DATA PRODUCTS

### 6.1 Raw Data (RAW)

**Description:** This is the first FITS data product produced by the DPS after receiving data from an instrument, where the data are in their unprocessed image state. To arrive at this stage, the DPS:

- Packaged the raw instrument data stream into FITS binary data format,
- Parsed the telemetry stream to obtain meta data and to assign FITS header information,
- Created a FITS file with the “raw” suffix, without regard to how the data would subsequently be used.

At this stage, the file suffix does not yet reflect the intended purpose of the data. The purpose is only apparent after additional data processing when another suffix (e.g. “bia”, “drk”, “dfl”, etc.) would replace the “raw” suffix. The raw FITS file is stored permanently into the data archive.

**Format:** The default file format for an UVIS CCD is shown in Figure 5-1 and discussed in Section 5.2.3, whereas for an NIR array, the format is shown in Figure 5-2 of Section 5.2.4.

**File:** <inst>\_raw.fits

Table 6.1: Data Product HDU: Raw Data

| Keyword  | Description   | Value/Table Format | Type   | HDU |
|----------|---|--------------------|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | RAW                | string | PRI |
| EXTNAME  | Name of the extension                                   | RAW                | string | PRI |
| OBSTYPE  | Observation type - imaging or spectroscopic             | IMAGING            | string | PRI |
| FILTER   | Filter name selected from filter wheel                  | CLEAR              | string | PRI |
| BUNIT    | Physical units of the array values                      | DN                 | string | PRI |
| XTENSION | Marks beginning of new HDU                              | IMAGE              | string | EXT |



## 6.2 Wavelength Calibration Exposure (WAV)

**Description:** This is an image containing 2-D spectral lines as observed from a spectral calibration light source, where the spectrum is dispersed along one dimension while spatial information is along the other dimension. This file is used to determine the wavelength solution of a corresponding science data spectral image. The spatial and dispersion directions might not necessarily be perfectly orthogonal, nor aligned with the detector pixel directions.

**Format:** The 2-D lamp spectral image is stored as a multi-extension file. The suffix ‘WAV’ is used to denote the file type.

**File:** <inst>\_wav.fits

Table 6.2: Data Product HDU: Wavelength Calibration Exposure

| Keyword  | Description   | Value/Table Format                          | Type   | HDU |
|----------|---|---|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | WAVELENGTH<br>CALIBRATION<br>SPECTRAL IMAGE | string | PRI |
| EXTNAME  | Name of the extension                                   | WAV   | string | PRI |
| OBSTYPE  | Observation type - imaging or spectroscopic             | SPECTROSCOPIC                               | string | PRI |
| FILTER   | Filter name selected from filter wheel                  | CLEAR                                       | string | PRI |

## 6.3 Template Calibration Lamp Spectra Table (LMP)

**Description:** The template calibration table contains spectra of the calibration lamp obtained at different operating voltage levels. These spectra are used to create template spectra or images, from which wavelength corrections can be determined, and wavelength solution determined.

**Format:** The lamp spectral calibration table is stored as a multi-extension file. The suffix 'LMP' is used to denote the file type.

**File:** <inst>\_lmp.fits

Table 6.3: Data Product HDU: Template Calibration Lamp Spectra Table

| Keyword  | Description   | Value/Table Format                        | Type   | HDU |
|----------|---|---|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | TEMPLATE CAL LAMP SPECTRA TABLE           | string | PRI |
| OBSTYPE  | Observation type - imaging or spectroscopic             | SPECTROSCOPIC                             | string | PRI |
| XTENSION | Marks beginning of new HDU                              | BINABLE                                   | string | EXT |
| EXTNAME  | Name of the extension                                   | LMP                                       | string | EXT |
| TTYPE1   | Column name   | SCLAMP                                    | string | EXT |
| TFORM1   | Column data format                                      | A20                                       | string | EXT |
| TDISP1   | Display format  | A20                                       | string | EXT |
| TDESC1   | Column description                                      | Name of calibration lamp that is on       | string | EXT |
| TTYPE2   | Column name   | LAMPVOLT                                  | string | EXT |
| TFORM2   | Column data format                                      | F6  | string | EXT |
| TDISP2   | Display format  | F6.2                                      | string | EXT |
| TUNIT2   | Column units  | voltage                                   | string | EXT |
| TDESC2   | Column description                                      | Spectral calibration lamp voltage setting | string | EXT |
| TTYPE3   | Column name   | NELEM                                     | string | EXT |
| TFORM3   | Column data format                                      | I10                                       | string | EXT |
| TDISP3   | Display format  | I10                                       | string | EXT |
| TDESC3   | Column description                                      | Number of data points in spectrum         | string | EXT |
| TTYPE4   | Column name   | Flux                                      | string | EXT |
| TFORM4   | Column data format                                      | F8  | string | EXT |
| TDISP4   | Display format  | F8.4                                      | string | EXT |
| TUNIT4   | Column units  | counts                                    | string | EXT |
| TDESC4   | Column description                                      | Lamp flux                                 | string | EXT |
| TTYPE5   | Column name   | DATESTAMP                                 | string | EXT |
| TFORM5   | Column data format                                      | A67                                       | string | EXT |
| TDISP5   | Display format  | A67                                       | string | EXT |
| TDESC5   | Column description                                      | Date stamp                                | string | EXT |
| TTYPE6   | Column name   | DESCRIP                                   | string | EXT |
| TFORM6   | Column data format                                      | A67                                       | string | EXT |
| TDISP6   | Display format  | A67                                       | string | EXT |
| TDESC6   | Column description                                      | Description of reference data             | string | EXT |

## 6.4 Association Table (ASN)

**Description:** This is a binary table containing information on associations of multiple exposures. Data files that need to be processed together to produce a product, or log files that are needed to make proper use of the data, constitute an association. Association tables are used to track the complex relationships that exist between multiple exposures, e.g. repeat observations, CR-split, dithered exposures, etc., for data processing purposes. Associations exist at all levels of data processing, from low-level data calibration to high-level mosaic image combination for science. Data associations can both be defined implicitly or explicitly, such as those that naturally exist between calibration reference files and raw data frames, or groups that are implied by choosing dither patterns. The DPS will use associations to perform quick-look data reduction that may involve image stacking, calibration (bias, dark, and flat-field removal) and sky subtraction. Associations are also used in the data archiving context, where it may be more useful to query and retrieve data as bundles rather than as individual files in a group.

An association has the same “ipppssoot” root name as an association data product, with a suffix “\_asn”. The last character in the root name will be a number between 0 and 9 to indicate association products and sub-products (see Figure 6 2 and Table 6 3). The content of the file is a table that lists all data files making up the association.

**Format:** [TBD] An association table has an ‘ASN’ file suffix.

**File:** <inst>\_asn.fits

Table 6.4: Data Product HDU: Association Table

| Keyword  | Description   | Value/Table Format                          | Type   | HDU |
|----------|---|---|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | ASSOCIATION TABLE                           | string | PRI |
| EXTNAME  | Name of the extension                                   | ASN   | string | PRI |
| XTENSION | Marks beginning of new HDU                              | BINTABLE                                    | string | EXT |
| TTYPE1   | Column name   | MEMNAME                                     | string | EXT |
| TFORM1   | Column data format                                      | A14   | string | EXT |
| TDISP1   | Display format  | A14   | string | EXT |
| TDESC1   | Column description                                      | Name of association member                  | string | EXT |
| TTYPE2   | Column name   | MEMTYPE                                     | string | EXT |
| TFORM2   | Column data format                                      | A14   | string | EXT |
| TDISP2   | Display format  | A14   | string | EXT |
| TDESC2   | Column description                                      | Type of association member                  | string | EXT |
| TTYPE3   | Column name   | MEMPRSNT                                    | string | EXT |
| TFORM3   | Column data format                                      | L   | string | EXT |
| TDISP3   | Display format  | L6.1  | string | EXT |
| TDESC3   | Column description                                      | Flag to indicate if member is present (T/F) | string | EXT |

## 6.5 Jitter File (JIF)

**Description:** This data product contains information on how the telescope behaved during an observation. Observation log files, sometimes called “jitter” files, record telemetries on pointing, jitter, guiding, open-loop tracking, laser operations, etc., during an observation. Observation log files are produced by the DPS; the information to produce the log files come by way of querying different data sources: the acquisition and guiding wavefront sensors, the mount control system, the telescope control system, on-instrument wavefront sensor, science instruments, etc.. Observation log files share the same rootname (Figure 6-2) as the main observation data except with the suffixes “\_jit” or “\_jif” (see Table 6-4).

The exact contents of this file is TBD, but generally speaking, this file contains a 2-D histogram of time-averaged telescope pointing excursion during an observation, stored in an image format. The amount of time averaging depends on the source of the data and the observing mode (natural seeing vs. adaptive optics) involved. The FITS header contains keywords providing information regarding the file structure, observation details, background light, telescope control system, jitter summary, problem flags, and warnings. The header values for extension 1+ will inherit keywords from the primary HDU.

**Format:** Content TBD

**File:** <inst>\_jif.fits

Table 6.5: Data Product HDU: Telescope Jitter Image

| Keyword  | Description   | Value/Table Format | Type   | HDU |
|----------|---|--------------------|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | JITTER HIS-TOGRAM  | string | PRI |
| EXTNAME  | Name of the extension                                   | JIF                | string | PRI |
| XTENSION | Marks beginning of new HDU                              | IMAGE              | string | EXT |

## 6.6 Telescope Jitter File (JIT)

## 6.7 Aperture Description Table (APD)

**Description:** The aperture description table describes the geometries of the apertures (size, orientation) and their offsets (in arcsec) from a reference position.

**Format:** Each row of the table contains the aperture name, size (length and width) of the aperture, offset from the center of aperture to the center of a reference (which is named in the header), and the orientation of the aperture's y-axis relative to a coordinate system that is fixed to the, ground, the telescope, or the instrument rotator, depending on the mounting location [TBD].

**File:** <inst>\_apd.fits

Table 6.6: Data Product HDU: Aperture Description Table

| Keyword  | Description   | Value/Table Format                        | Type   | HDU |
|----------|---|---|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | APERTURE DESCRIPTION TABLE                | string | PRI |
| XTENSION | Marks beginning of new HDU                              | BINABLE                                   | string | EXT |
| EXTNAME  | Name of the extension                                   | APT                                       | string | EXT |
| TTYPE1   | Column name   | APERTURE                                  | string | EXT |
| TFORM1   | Column data format                                      | A20                                       | string | EXT |
| TDISP1   | Display format  | A20                                       | string | EXT |
| TDESC1   | Column description                                      | Name of aperture                          | string | EXT |
| TTYPE2   | Column name   | WIDTH1                                    | string | EXT |
| TFORM2   | Column data format                                      | F8  | string | EXT |
| TDISP2   | Display format  | F8.5                                      | string | EXT |
| TUNIT2   | Column units  | arcsec                                    | string | EXT |
| TDESC2   | Column description                                      | Width along axis 1                        | string | EXT |
| TTYPE3   | Column name   | WIDTH2                                    | string | EXT |
| TFORM3   | Column data format                                      | F8  | string | EXT |
| TDISP3   | Display format  | F8.5                                      | string | EXT |
| TUNIT3   | Column units  | arcsec                                    | string | EXT |
| TDESC3   | Column description                                      | Width along axis 2                        | string | EXT |
| TTYPE4   | Column name   | ANGLE                                     | string | EXT |
| TFORM4   | Column data format                                      | F10                                       | string | EXT |
| TDISP4   | Display format  | F10.3                                     | string | EXT |
| TUNIT4   | Column units  | degrees                                   | string | EXT |
| TDESC4   | Column description                                      | Orientation of long or y-axis of aperture | string | EXT |
| TTYPE5   | Column name   | OFFSET1                                   | string | EXT |
| TFORM5   | Column data format                                      | F12                                       | string | EXT |
| TDISP5   | Display format  | F12.5                                     | string | EXT |
| TUNIT5   | Column units  |   | string | EXT |
| TDESC5   | Column description                                      | Offset from reference position in axis 1  | string | EXT |
| TTYPE6   | Column name   | OFFSET2                                   | string | EXT |
| TFORM6   | Column data format                                      | F12                                       | string | EXT |
| TDISP6   | Display format  | F12.5                                     | string | EXT |
| TUNIT6   | Column units  |   | string | EXT |

Continued on next page

Table 6.6 – continued from previous page

| Keyword | Description        | Value/Table Format                       | Type   | HDU |
|---------|--------------------|--|--------|-----|
| TDESC6  | Column description | Offset from reference position in axis 2 | string | EXT |
| TTYPE7  | Column name        | DATESTAMP                                | string | EXT |
| TFORM7  | Column data format | A67                                      | string | EXT |
| TDISP7  | Display format     | A67                                      | string | EXT |
| TDESC7  | Column description | Date stamp                               | string | EXT |
| TTYPE8  | Column name        | DESCRIP                                  | string | EXT |
| TFORM8  | Column data format | A67                                      | string | EXT |
| TDISP8  | Display format     | A67                                      | string | EXT |
| TDESC8  | Column description | Description of reference data            | string | EXT |

## 6.8 2D Spectrum Distortion Correction Table (SDC)

**Description:** This table consists of a set of WCS information used to rectify and linearize observed spectra in a 2-D image. Each set of WCS corresponds to a spectral order for a long slit spectrum, spectrum aperture ID for an integral field or multi-slit/fiber spectral image.

**Format:** The columns of the table are: optical element, central wavelength, spectral order, the pixel position of the center of the spectrum, and the WCS information of the output rectified spectra.

**File:** <inst>\_sdc.fits

Table 6.7: Data Product HDU: 2D Spectrum Distortion Correction

| Keyword  | Description   | Value/Table Format   | Type   | HDU |
|----------|---|--|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | 2-D SPECTRUM DISTORTION CORRECTION TABLE                                       | string | PRI |
| XTENSION | Marks beginning of new HDU                              | BINABLE  | string | EXT |
| EXTNAME  | Name of the extension                                   | SDC  | string | EXT |
| TTYPE1   | Column name   | OPT_ELEM   | string | EXT |
| TFORM1   | Column data format                                      | A20  | string | EXT |
| TDISP1   | Display format  | A20  | string | EXT |
| TDESC1   | Column description                                      | Spectroscopic element in the grating wheel                                     | string | EXT |
| TTYPE2   | Column name   | CENWAVE  | string | EXT |
| TFORM2   | Column data format                                      | F8   | string | EXT |
| TDISP2   | Display format  | F8.2   | string | EXT |
| TUNIT2   | Column units  | Angstrom   | string | EXT |
| TDESC2   | Column description                                      | Central wavelength   | string | EXT |
| TTYPE3   | Column name   | SPORDER  | string | EXT |
| TFORM3   | Column data format                                      | I3   | string | EXT |
| TDISP3   | Display format  | I3   | string | EXT |
| TDESC3   | Column description                                      | Spectral order   | string | EXT |
| TTYPE4   | Column name   | APERTURE   | string | EXT |
| TFORM4   | Column data format                                      | A20  | string | EXT |
| TDISP4   | Display format  | A20  | string | EXT |
| TUNIT4   | Column units  |  | string | EXT |
| TDESC4   | Column description                                      | Spectral aperture ID   | string | EXT |
| TTYPE5   | Column name   | WCENTER  | string | EXT |
| TFORM5   | Column data format                                      | F10  | string | EXT |
| TDISP5   | Display format  | F10.3  | string | EXT |
| TUNIT5   | Column units  | pixel  | string | EXT |
| TDESC5   | Column description                                      | Nominal pixel (along dispersion direction) corresponding to center of spectrum | string | EXT |
| TTYPE6   | Column name   | NPIX1  | string | EXT |
| TFORM6   | Column data format                                      | I5   | string | EXT |
| TDISP6   | Display format  | I5   | string | EXT |
| TUNIT6   | Column units  | pixel  | string | EXT |

Continued on next page

Table 6.7 – continued from previous page

| Keyword | Description        | Value/Table Format   | Type   | HDU |
|---------|--------------------|--|--------|-----|
| TDESC6  | Column description | Number of axis 1<br>pixels in rectified im-<br>age           | string | EXT |
| TTYPE7  | Column name        | NPIX2  | string | EXT |
| TFORM7  | Column data format | I5   | string | EXT |
| TDISP7  | Display format     | I5   | string | EXT |
| TDESC7  | Column description | Number of axis 1<br>pixels in rectified im-<br>age           | string | EXT |
| TTYPE8  | Column name        | CRPIX1   | string | EXT |
| TFORM8  | Column data format | I5   | string | EXT |
| TDISP8  | Display format     | I5   | string | EXT |
| TUNIT8  | Column units       | pixel  | string | EXT |
| TDESC8  | Column description | Axis 1 coordinate<br>a reference pixel in<br>rectified image | string | EXT |
| TTYPE9  | Column name        | CRPIX2   | string | EXT |
| TFORM9  | Column data format | I5   | string | EXT |
| TDISP9  | Display format     | I5   | string | EXT |
| TUNIT9  | Column units       | pixel  | string | EXT |
| TDESC9  | Column description | Axis 2 coordinate<br>a reference pixel in<br>rectified image | string | EXT |
| TTYPE10 | Column name        | CRVAL1   | string | EXT |
| TFORM10 | Column data format | F10  | string | EXT |
| TDISP10 | Display format     | F10.3  | string | EXT |
| TUNIT10 | Column units       | Angstrom   | string | EXT |
| TDESC10 | Column description | Axis 1 value at refer-<br>ence pixel in rectified<br>image   | string | EXT |
| TTYPE11 | Column name        | CRVAL2   | string | EXT |
| TFORM11 | Column data format | F12  | string | EXT |
| TDISP11 | Display format     | F12.5  | string | EXT |
| TUNIT11 | Column units       | arcsec   | string | EXT |
| TDESC11 | Column description | Axis 2 value at refer-<br>ence pixel in rectified<br>image   | string | EXT |
| TTYPE12 | Column name        | CDEL1  | string | EXT |
| TFORM12 | Column data format | F8   | string | EXT |
| TDISP12 | Display format     | F8.4   | string | EXT |
| TUNIT12 | Column units       | Angstrom/pixel   | string | EXT |
| TDESC12 | Column description | Axis 1 pixel spacing<br>in rectified image                   | string | EXT |
| TTYPE13 | Column name        | CDEL2  | string | EXT |
| TFORM13 | Column data format | F8   | string | EXT |
| TDISP13 | Display format     | F8.5   | string | EXT |
| TUNIT13 | Column units       | arcsec/pixel   | string | EXT |
| TDESC13 | Column description | Axis 2 pixel spacing<br>in rectified image                   | string | EXT |
| TTYPE14 | Column name        | DATESTAMP  | string | EXT |

Continued on next page



Table 6.7 – continued from previous page

| Keyword  | Description        | Value/Table Format            | Type   | HDU |
|----------|--------------------|-------------------------------|--------|-----|
| TFORM14  | Column data format | A67                           | string | EXT |
| TDISP14  | Display format     | A67                           | string | EXT |
| TDESC14  | Column description | Date stamp                    | string | EXT |
| TTYPER15 | Column name        | DESCRIP                       | string | EXT |
| TFORM15  | Column data format | A67                           | string | EXT |
| TDISP15  | Display format     | A67                           | string | EXT |
| TDESC15  | Column description | Description of reference data | string | EXT |

## 6.9 Dispersion Coefficients Table (DSP)

**Description:** This table consists of dispersion coefficients of a nominal, calibrated, dispersion solution, to apply to extracted 1-D spectra.

**Format:** The columns of the table are: optical element (e.g. grating), central wavelength, spectral order, aperture ID, reference aperture name, and coefficients to a dispersion function.

**File:** <inst>\_dsp.fits

Table 6.8: Data Product HDU: Dispersion Coefficients Table

| Keyword  | Description   | Value/Table Format  | Type   | HDU |
|----------|---|---|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | DISPERSION<br>COEFFICIENTS<br>TABLE   | string | PRI |
| XTENSION | Marks beginning of new HDU                              | BINABLE   | string | EXT |
| EXTNAME  | Name of the extension                                   | DSP   | string | EXT |
| TTYPE1   | Column name   | OPT_ELEM  | string | EXT |
| TFORM1   | Column data format                                      | A20   | string | EXT |
| TDISP1   | Display format  | A20   | string | EXT |
| TDESC1   | Column description                                      | Spectroscopic ele-<br>ment in the grating<br>wheel                                      | string | EXT |
| TTYPE2   | Column name   | CENWAVE   | string | EXT |
| TFORM2   | Column data format                                      | F8  | string | EXT |
| TDISP2   | Display format  | F8.2  | string | EXT |
| TUNIT2   | Column units  | Angstrom  | string | EXT |
| TDESC2   | Column description                                      | Central wavelength  | string | EXT |
| TTYPE3   | Column name   | SPORDER   | string | EXT |
| TFORM3   | Column data format                                      | I3  | string | EXT |
| TDISP3   | Display format  | I3  | string | EXT |
| TDESC3   | Column description                                      | Spectral order  | string | EXT |
| TTYPE4   | Column name   | APERTURE  | string | EXT |
| TFORM4   | Column data format                                      | A20   | string | EXT |
| TDISP4   | Display format  | A20   | string | EXT |
| TUNIT4   | Column units  |   | string | EXT |
| TDESC4   | Column description                                      | Spectral aperture ID  | string | EXT |
| TTYPE5   | Column name   | REF_APER  | string | EXT |
| TFORM5   | Column data format                                      | A12   | string | EXT |
| TDISP5   | Display format  | A12   | string | EXT |
| TUNIT5   | Column units  |   | string | EXT |
| TDESC5   | Column description                                      | Name of reference<br>aperture   | string | EXT |
| TTYPE6   | Column name   | WCENTER   | string | EXT |
| TFORM6   | Column data format                                      | F10   | string | EXT |
| TDISP6   | Display format  | F10.3   | string | EXT |
| TUNIT6   | Column units  | pixel   | string | EXT |
| TDESC6   | Column description                                      | Nominal pixel (along<br>dispersion direction)<br>corresponding to<br>center of spectrum | string | EXT |
| TTYPE7   | Column name   | NCOEFF  | string | EXT |

Continued on next page

Table 6.8 – continued from previous page

| Keyword | Description        | Value/Table Format                            | Type   | HDU |
|---------|--------------------|---|--------|-----|
| TFORM7  | Column data format | I2  | string | EXT |
| TDISP7  | Display format     | I2  | string | EXT |
| TDESC7  | Column description | Number of coefficients in dispersion solution | string | EXT |
| TTYPE8  | Column name        | COEFF   | string | EXT |
| TFORM8  | Column data format | E10   | string | EXT |
| TDISP8  | Display format     | E10.7   | string | EXT |
| TUNIT8  | Column units       |   | string | EXT |
| TDESC8  | Column description | Dispersion solution coefficients              | string | EXT |
| TTYPE9  | Column name        | DATESTAMP                                     | string | EXT |
| TFORM9  | Column data format | A67   | string | EXT |
| TDISP9  | Display format     | A67   | string | EXT |
| TDESC9  | Column description | Date stamp                                    | string | EXT |
| TTYPE10 | Column name        | DESCRIP                                       | string | EXT |
| TFORM10 | Column data format | A67   | string | EXT |
| TDISP10 | Display format     | A67   | string | EXT |
| TDESC10 | Column description | Description of reference data                 | string | EXT |

## 6.10 1D Spectrum Trace Table (1DT)

**Description:** This table defines the spectral trace prior to extracting 1-D spectrum. If a spectrum is dispersed mostly along the x-axis, then the table consists of y-displacements of the spectrum as a function of x that defines the spectral trace.

**Format:** The dispersion column consists: Optical element, central wavelength, aperture ID for multi-fiber/slit spectra, the reference position of the aperture on a 2-D spectral image, spectral order, and an array of y-displacements of the spectrum as a function of nominal dispersion position (often x-position).

**File:** <inst>\_1dt.fits

Table 6.9: Data Product HDU: 1D Spectrum Trace Table

| Keyword  | Description   | Value/Table Format  | Type   | HDU |
|----------|---|---|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | 1-D SPECTRUM TRACE TABLE  | string | PRI |
| XTENSION | Marks beginning of new HDU                              | BINABLE   | string | EXT |
| EXTNAME  | Name of the extension                                   | 1DT   | string | EXT |
| TTYPE1   | Column name   | OPT_ELEM  | string | EXT |
| TFORM1   | Column data format                                      | A20   | string | EXT |
| TDISP1   | Display format  | A20   | string | EXT |
| TDESC1   | Column description                                      | Spectroscopic element in the grating wheel  | string | EXT |
| TTYPE2   | Column name   | CENWAVE   | string | EXT |
| TFORM2   | Column data format                                      | F8  | string | EXT |
| TDISP2   | Display format  | F8.2  | string | EXT |
| TUNIT2   | Column units  | Angstrom  | string | EXT |
| TDESC2   | Column description                                      | Central wavelength  | string | EXT |
| TTYPE3   | Column name   | APERTURE  | string | EXT |
| TFORM3   | Column data format                                      | A20   | string | EXT |
| TDISP3   | Display format  | A20   | string | EXT |
| TDESC3   | Column description                                      | Spectral aperture ID  | string | EXT |
| TTYPE4   | Column name   | SPORDER   | string | EXT |
| TFORM4   | Column data format                                      | I3  | string | EXT |
| TDISP4   | Display format  | I3  | string | EXT |
| TUNIT4   | Column units  |   | string | EXT |
| TDESC4   | Column description                                      | Spectral order  | string | EXT |
| TTYPE5   | Column name   | A1CENTER  | string | EXT |
| TFORM5   | Column data format                                      | F10   | string | EXT |
| TDISP5   | Display format  | F10.3   | string | EXT |
| TUNIT5   | Column units  | pixel   | string | EXT |
| TDESC5   | Column description                                      | Nominal pixel (along dispersion direction) corresponding to wavelength center of spectrum | string | EXT |
| TTYPE6   | Column name   | A2CENTER  | string | EXT |
| TFORM6   | Column data format                                      | F10   | string | EXT |
| TDISP6   | Display format  | F10.4   | string | EXT |
| TUNIT6   | Column units  | pixel   | string | EXT |

Continued on next page

Table 6.9 – continued from previous page

| Keyword | Description        | Value/Table Format  | Type   | HDU |
|---------|--------------------|---|--------|-----|
| TDESC6  | Column description | Nominal pixel corresponding to spatial center of spectrum | string | EXT |
| TTYPE7  | Column name        | A2DISPL   | string | EXT |
| TFORM7  | Column data format | F10   | string | EXT |
| TDISP7  | Display format     | F10.4   | string | EXT |
| TUNIT7  | Column units       |   | string | EXT |
| TDESC7  | Column description | Spectral displacement along axis 2                        | string | EXT |
| TTYPE8  | Column name        | DATESTAMP   | string | EXT |
| TFORM8  | Column data format | A67   | string | EXT |
| TDISP8  | Display format     | A67   | string | EXT |
| TDESC8  | Column description | Date stamp  | string | EXT |
| TTYPE9  | Column name        | DESCRIP   | string | EXT |
| TFORM9  | Column data format | A67   | string | EXT |
| TDISP9  | Display format     | A67   | string | EXT |
| TDESC9  | Column description | Description of reference data                             | string | EXT |

## 6.11 1D Spectral Extraction Parameter Table (1DX)

**Description:** This table describes the science and background extraction apertures and the functions used in extractions.

**Format:** The extraction apertures are defined by the height of the box (EXTRSIZE, BK1SIZE, BK2SIZE), the extraction algorithm (XTRACALG, polynomial function), and functional coefficients (SLTCOEFF, BKTCOEFF).

**File:** <inst>\_1dx.fits

Table 6.10: Data Product HDU: 1D Spectral Extraction Parameter Table

| Keyword  | Description   | Value/Table Format   | Type   | HDU |
|----------|---|--|--------|-----|
| FILETYPE | Type of data found in data file (SCI, CALIB, RAW, etc.) | 1-D SPECTRAL EXTRACTION PARAMETER TABLE                    | string | PRI |
| XTENSION | Marks beginning of new HDU                              | BINABLE  | string | EXT |
| EXTNAME  | Name of the extension                                   | 1DX  | string | EXT |
| TTYPE1   | Column name   | OPT_ELEM   | string | EXT |
| TFORM1   | Column data format                                      | A20  | string | EXT |
| TDISP1   | Display format  | A20  | string | EXT |
| TDESC1   | Column description                                      | Spectroscopic element in the grating wheel                 | string | EXT |
| TTYPE2   | Column name   | CENWAVE  | string | EXT |
| TFORM2   | Column data format                                      | F8   | string | EXT |
| TDISP2   | Display format  | F8.2   | string | EXT |
| TUNIT2   | Column units  | Angstrom   | string | EXT |
| TDESC2   | Column description                                      | Central wavelength   | string | EXT |
| TTYPE3   | Column name   | APERTURE   | string | EXT |
| TFORM3   | Column data format                                      | A20  | string | EXT |
| TDISP3   | Display format  | A20  | string | EXT |
| TDESC3   | Column description                                      | Spectral aperture ID                                       | string | EXT |
| TTYPE4   | Column name   | SPORDER  | string | EXT |
| TFORM4   | Column data format                                      | I3   | string | EXT |
| TDISP4   | Display format  | I3   | string | EXT |
| TUNIT4   | Column units  |  | string | EXT |
| TDESC4   | Column description                                      | Spectral order   | string | EXT |
| TTYPE5   | Column name   | EXTRSIZE   | string | EXT |
| TFORM5   | Column data format                                      | F8   | string | EXT |
| TDISP5   | Display format  | F8.3   | string | EXT |
| TUNIT5   | Column units  | pixel  | string | EXT |
| TDESC5   | Column description                                      | Height of spectrum extraction box                          | string | EXT |
| TTYPE6   | Column name   | NCOEFFSL   | string | EXT |
| TFORM6   | Column data format                                      | I3   | string | EXT |
| TDISP6   | Display format  | I3   | string | EXT |
| TUNIT6   | Column units  |  | string | EXT |
| TDESC6   | Column description                                      | Number of coefficients in solution to slit tilt correction | string | EXT |
| TTYPE7   | Column name   | SLTCOEFF   | string | EXT |
| TFORM7   | Column data format                                      | E8   | string | EXT |

Continued on next page

Table 6.10 – continued from previous page

| Keyword | Description        | Value/Table Format   | Type   | HDU |
|---------|--------------------|--|--------|-----|
| TDISP7  | Display format     | E8.6   | string | EXT |
| TUNIT7  | Column units       |  | string | EXT |
| TDESC7  | Column description | Spectrum extraction coefficients                           | string | EXT |
| TTYPE8  | Column name        | BK1SIZE  | string | EXT |
| TFORM8  | Column data format | F8   | string | EXT |
| TDISP8  | Display format     | F8.3   | string | EXT |
| TUNIT8  | Column units       | pixel  | string | EXT |
| TDESC8  | Column description | Height of back-ground extraction box 1                     | string | EXT |
| TTYPE9  | Column name        | BK2SIZE  | string | EXT |
| TFORM9  | Column data format | F8   | string | EXT |
| TDISP9  | Display format     | F8.3   | string | EXT |
| TUNIT9  | Column units       | pixel  | string | EXT |
| TDESC9  | Column description | Height of back-ground extraction box 2                     | string | EXT |
| TTYPE10 | Column name        | BK1OFFST   | string | EXT |
| TFORM10 | Column data format | F8   | string | EXT |
| TDISP10 | Display format     | F8.3   | string | EXT |
| TUNIT10 | Column units       | pixel  | string | EXT |
| TDESC10 | Column description | Offset of background extraction box 1 from spectrum        | string | EXT |
| TTYPE11 | Column name        | BK2OFFST   | string | EXT |
| TFORM11 | Column data format | F8   | string | EXT |
| TDISP11 | Display format     | F8.3   | string | EXT |
| TUNIT11 | Column units       | pixel  | string | EXT |
| TDESC11 | Column description | Offset of background extraction box 2 from spectrum        | string | EXT |
| TTYPE12 | Column name        | NCOEFFBK   | string | EXT |
| TFORM12 | Column data format | I3   | string | EXT |
| TDISP12 | Display format     | I3   | string | EXT |
| TUNIT12 | Column units       |  | string | EXT |
| TDESC12 | Column description | Number of coefficients in solution to slit tilt correction | string | EXT |
| TTYPE13 | Column name        | BKTCOEFF   | string | EXT |
| TFORM13 | Column data format | E8   | string | EXT |
| TDISP13 | Display format     | E8.6   | string | EXT |
| TUNIT13 | Column units       |  | string | EXT |
| TDESC13 | Column description | Background extraction coefficients                         | string | EXT |
| TTYPE14 | Column name        | BACKORD  | string | EXT |
| TFORM14 | Column data format | I3   | string | EXT |
| TDISP14 | Display format     | I3   | string | EXT |
| TUNIT14 | Column units       |  | string | EXT |

Continued on next page

Table 6.10 – continued from previous page

| Keyword | Description        | Value/Table Format                    | Type   | HDU |
|---------|--------------------|---------------------------------------|--------|-----|
| TDESC14 | Column description | Order of polynomial fit to background | string | EXT |
| TTYPE15 | Column name        | XTRACALG                              | string | EXT |
| TFORM15 | Column data format | A20                                   | string | EXT |
| TDISP15 | Display format     | A20                                   | string | EXT |
| TDESC15 | Column description | Extraction algorithm to use           | string | EXT |
| TTYPE16 | Column name        | DATESTAMP                             | string | EXT |
| TFORM16 | Column data format | A67                                   | string | EXT |
| TDISP16 | Display format     | A67                                   | string | EXT |
| TDESC16 | Column description | Date stamp                            | string | EXT |
| TTYPE17 | Column name        | DESCRIP                               | string | EXT |
| TFORM17 | Column data format | A67                                   | string | EXT |
| TDISP17 | Display format     | A67                                   | string | EXT |
| TDESC17 | Column description | Description of reference data         | string | EXT |



**REFERENCES**

# List of Figures

# List of Tables

|      |   |    |
|------|---|----|
| 3.1  | Primary HDU: Basic FITS Primary Header Data Unit . . . . .          | 3  |
| 3.2  | Extension HDU: Basic FITS Image Extension . . . . .                 | 4  |
| 3.3  | Extension HDU: Base ASCII Table . . . . .                           | 5  |
| 3.4  | Extension HDU: Basic Binary Table Extension . . . . .               | 6  |
| 4.1  | Primary HDU: Base Exposure . . . . .                                | 7  |
| 4.2  | Extension HDU: Base Exposure . . . . .                              | 12 |
| 4.3  | Extension HDU: Base Calibration Reference Table . . . . .           | 14 |
| 5.1  | Data Product HDU: Bias Frame . . . . .                              | 15 |
| 5.2  | Data Product HDU: Dark Frame . . . . .                              | 16 |
| 5.3  | Data Product HDU: Dome Flat Field Frame . . . . .                   | 17 |
| 5.4  | Data Product HDU: Night-Sky Flat Field Frame . . . . .              | 18 |
| 5.5  | Data Product HDU: Twilight Flat Field Frame . . . . .               | 19 |
| 5.6  | Data Product HDU: Background Illumination Pattern Frame . . . . .   | 20 |
| 5.7  | Data Product HDU: Bad Pixel Mask Frame . . . . .                    | 21 |
| 5.8  | Data Product HDU: Post Flash Image . . . . .                        | 22 |
| 5.9  | Data Product HDU: Analog-to-Digital Table . . . . .                 | 23 |
| 5.10 | Data Product HDU: Bad Pixel Table . . . . .                         | 24 |
| 5.11 | Data Product HDU: Detector Characteristics Table . . . . .          | 25 |
| 5.12 | Data Product HDU: Cosmic Ray Rejection Parameters . . . . .         | 27 |
| 5.13 | Data Product HDU: Image Distortion Coefficients . . . . .           | 28 |
| 5.14 | Data Product HDU: Overscan Region . . . . .                         | 30 |
| 5.15 | Data Product HDU: Photometric Calibration . . . . .                 | 33 |
| 5.16 | Data Product HDU: Aperture Throughput Table . . . . .               | 35 |
| 6.1  | Data Product HDU: Raw Data . . . . .                                | 37 |
| 6.2  | Data Product HDU: Wavelength Calibration Exposure . . . . .         | 38 |
| 6.3  | Data Product HDU: Template Calibration Lamp Spectra Table . . . . . | 39 |
| 6.4  | Data Product HDU: Association Table . . . . .                       | 40 |
| 6.5  | Data Product HDU: Telescope Jitter Image . . . . .                  | 41 |
| 6.6  | Data Product HDU: Aperture Description Table . . . . .              | 42 |
| 6.7  | Data Product HDU: 2D Spectrum Distortion Correction . . . . .       | 44 |
| 6.8  | Data Product HDU: Dispersion Coefficients Table . . . . .           | 47 |
| 6.9  | Data Product HDU: 1D Spectrum Trace Table . . . . .                 | 49 |
| 6.10 | Data Product HDU: 1D Spectral Extraction Parameter Table . . . . .  | 51 |